



Movavi Screen Capture Studio 7

What do you need help with today?

[Removing trial restrictions](#)

Activate Movavi Screen Capture Studio to use unlimited capture and save videos without a watermark

[Recording screen](#)

Capture any fragment of your screen or the full desktop.

[Capturing online video](#)

Record video from online video websites such as YouTube or Vimeo.

[Capturing Skype calls](#)

Record Skype calls with sound from both ends.

[Recording only audio](#)

Record any sound from a device or music on your computer.

[Using Screen Capture](#)

[Editing video](#)

Create a movie from videos and photos

[Creating a video tutorial](#)

Record your screen and add annotations

[Cutting video](#)

Split video clips into parts

[Exporting videos](#)

Save your finished movie

[Using the Video Editor](#)

Need more help?

Write to us at support@movavi.com

Table of Contents

Removing trial restrictions4

 Getting an activation key.....5

 Activating Screen Capture Studio6

 Activating without Internet access7

Recording screen activity9

Capturing online video.....12

Capturing Skype calls.....14

Capturing video from players16

Making a video tutorial18

Making a movie21

Recording audio.....25

Using Screen Capture27

 Capture area28

 Sound30

 Scheduling.....31

 Highlighting events.....32

 Mouse cursor effects33

 Recording keystrokes34

 Starting the recording35

 Saving the captured video.....37

 Choosing a resolution.....39

 Reducing output size.....41

 Publishing videos online.....42

 Editing the captured video.....43

 Recording and saving audio.....44

 Saving previously captured files.....46

 Saving screenshots.....47

 Screen Capture preferences48

 General preferences49

 File preferences50

 Keyboard shortcuts.....51

 Video preferences.....52

 Audio preferences.....53

Using the Video Editor54

 New project setup.....55

 Adding media files57

 Recoding video59

 Recording audio.....61

 Importing AVCHD video.....62

Using the Timeline.....64

Working with video and images66

 Cutting video68

 Applying filters.....69

 Adding overlays70

Editing tools72

 Video volume75

 Speed.....76

 Changing image duration77

 Fading video and audio.....78

 Color adjustments.....79

 Cropping video.....80

 Rotate and flip clips.....81

 Zooming clips.....82

 Chroma key.....83

 Highlight and conceal84

 Stabilizing video86

Working with audio87

 Adding audio.....89

 Audio tracks91

 Volume levels.....93

 Cutting audio.....94

 Looping audio95

 Extracting audio from videos.....96

Adding titles97

Adding transitions99

Creating slideshows.....101

How to get rid of black bars103

Exporting videos105

 Export only audio.....107

 Export for devices.....108

 Export online.....109

Saving and opening projects.....110

Finding missing files111

Project settings112

Program preferences115

Help and support116

System requirements	117
Input formats	118
Output formats	119
Updating graphics card drivers	120
Hardware acceleration	121

Removing trial restrictions


When you first start your copy of Movavi Screen Capture Studio, it will be running in **LIMITED TRIAL MODE**. In trial mode, you can try out all of the main features, but the following trial restrictions will apply:

TRIAL VERSION	FULL VERSION
<div><div></div><div>Movavi Screen Capture Studio will stop working after 7 days</div></div>	<div><div></div><div>Lifetime license</div></div>
<div><div></div><div>A watermark with the words ' trial version' will be added to all exported videos</div></div>	<div><div></div><div>No annoying watermarks</div></div>
<div><div></div><div>Capture time is limited to 2 minutes per video</div></div>	<div><div></div><div>Unlimited capture time</div></div>
	<div><div></div><div>Free updates</div></div>
	<div><div></div><div>Discounts on other Movavi products and upgrades</div></div>

To upgrade to the full version, follow the instructions below to activate Movavi Screen Capture Studio:


Step 1: Buy activation key

- Click the button below to go to the purchase page and click the **Buy Now** button there.
- You will be taken to our web store. Fill in your billing information and payment options and proceed with the purchase form. **IMPORTANT!** Be sure to enter a valid e-mail address: it will be used to deliver your activation key.
- Once you have placed your order, you will shortly receive a confirmation for your order and an e-mail from *support@movavi.com* containing your activation key.




Step 2: Open the activation window

- Open Movavi Screen Capture Studio
- On the capture control panel window, open the **Help** menu and select **Activate Software**. The activation window will open:



Step 3: Enter your activation key

- Enter the activation key into the corresponding box.
- Click **Activate** to complete the activation.



Having problems with activation?

If activation is not working as expected, try the following:

- Make sure that the activation key is entered correctly and is intended for the program you are activating.
- Try [activating offline via e-mail](#).
- Contact us at support@movavi.com and we'll help you solve the problem!

Activating without Internet access

If the computer you have installed Movavi Screen Capture Studio on is not connected to the Internet, you can activate the program via e-mail.

[See detailed instructions](#)


Getting an activation key

You can get an activation key either from our official website or from any of our partners in your region. Follow the steps below to buy an activation key from the Movavi website:

Step 1: Go to the purchase page

To open the purchase page for Movavi Screen Capture Studio:

- In the Help menu, choose **Buy Activation Key**, or
- Follow the link below...



Step 2: Choose a license type

- If you plan to use Movavi Screen Capture Studio at home, click **Buy Now** on the purchase page to proceed with buying the personal license.
- If you plan to use Movavi Screen Capture Studio at work, in a government institution, or gain profit in any way, click **Business license** on the purchase page.

After that, you will be redirected to an online store depending on your region and the available payment methods. All of our vendor partners are secure and completely safe.

Step 3: Fill in your billing details

1. Choose any of the available payment methods.
2. Fill in the information required on the page.
3. Enter a valid e-mail address. This e-mail will be used to deliver your activation key.

Step 4: Get your activation key

After the purchase has been verified, you will receive a letter containing your activation key. Now you can use it to activate the program.

[Activation instructions](#)

[Activating without Internet access](#)

If you haven't received your activation key within the hour:

- Check the **Spam** folder of your mailbox
- [Contact support](#)

Activating Screen Capture Studio


Activating Movavi Screen Capture Studio will allow you to remove all of the trial restrictions and use the program forever.

You will need:

- Movavi Screen Capture Studio activation key. You should receive your key via e-mail right after your purchase is completed. Don't have a key? [Buy now](#)
- Internet access. Don't have Internet access? [See this guide on offline activation](#)


Step 1: Open the activation window

1. Launch Movavi Screen Capture Studio, Movavi Screen Capture, or the Video Editor.
2. Open the **Help** menu and select **Activate Software**.



Step 2: Enter your activation key

1. Enter or paste your activation key into the corresponding box of the Activation window.
2. Click **Activate** to verify your activation key.



If you have entered the key correctly, you should see a message confirming successful activation. Click **OK** to complete the activation process and restart the program.

If online activation fails, try the following:

- Check that the activation key is entered correctly and is intended for the program you are activating.
- Try [offline activation](#).

If you have any questions or problems while activating your Movavi software, please don't hesitate to [contact our support team](#).

Activating without Internet access


Activating Movavi Screen Capture Studio will allow you to remove all of the trial restrictions and use the program forever. If you don't have Internet access on your computer, you can use any other computer or mobile device to complete the steps that require a connection.

You will need:

- Movavi Screen Capture Studio activation key. You should receive your key via e-mail right after your purchase is completed. Don't have a key? [Buy now](#)
- A device or another computer that can be used to send and receive e-mail


Step 1: Open the activation window

1. Launch Movavi Screen Capture Studio, Movavi Screen Capture, or the Video Editor.
2. Open the **Help** menu and select **Activate Software**. The following dialog box will appear:




Step 2: Enter your activation key

1. Enter or paste your activation key into the corresponding field.
2. Select the **Activate offline** option.
3. Click **Activate** to proceed to the next step.




Step 3: Send an e-mail with the provided information


The next window contains important activation information that you will need to send us via e-mail in order to activate your program.



1. Click the **Copy** button to copy the information in the window. If necessary, save or transfer this information to the computer or device that you will be sending the e-mail from.
2. On the computer with an Internet connection, open your mail client and compose a new e-mail. Paste the information you've copied earlier into the message body and send this e-mail to reg@movavi.com. The activation server will then verify your activation key and send you an automatic response containing a **registration key**, which you will need to enter into the **Activation** window. You should receive the server's reply within an hour.



- Step 4: Enter your registration key**
1. When you have received your registration key, save it and go back to the Activation window.
 2. Enter the registration key into the corresponding box.
 3. Click **Activate** to submit the information.



If everything is correct, you will see a successful activation message. Click **Finish** to complete the activation and close the activation wizard.

Once activation is complete, you may be asked to restart the application. If you have entered the key correctly, you should see a message confirming successful activation. Click **OK** to complete the activation process and restart the program.

If offline activation doesn't work:


- Make sure you have entered the activation key and the registration key correctly and try again
- Check that you are activating the right application.
- Make sure you have administrator rights on your computer

If you have any questions or problems while activating your Movavi software, feel free to contact us and we'll help you out!
Our e-mail: support@movavi.com

Recording screen activity

Step 1: Launch the Screen Capture module

Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.




Step 2: Choose the capture area

First, you'll need to set which part of the screen you want to record.

To record the full screen

Open the list in the left part of the control panel and choose your display under **Full Screen**.



To record a window

On the capture control panel, click the crosshair button and then click on the window you want to capture. An orange capture frame will appear around the window.



To record a custom fragment

On the capture control panel, click the crosshair button. Then, click and drag to draw the capture area on the screen.

[Learn more about the capture area](#)




Step 3: Choose audio sources

Next, we'll select what sounds you want to be heard in your video.

Music or sounds from your computer

To enable recording sounds from your computer (any music, videos, applications, and alerts), click the **System Audio** button. Use the slider to the left of the System Audio button to manage the volume of the recording.




Microphone or audio device

To record from an external device, click the microphone button and select the device you want to use from the list below it. Use the slider to the left of the microphone button to manage the device's volume.


[Learn more about audio](#)




Step 4: Extras

If you want to limit the length of the recording or record at a later time, use the **Capture time options** button: 

[Learn more](#)

If you want to display your mouse during capture, click the **Cursor options** button: 


[Learn more](#)

If you want to show which keys you pressed during recording, click the **Record keystrokes** button: 

[Learn more](#)


Step 5: Set the volume

Before you start a recording, you can adjust a volume level for both system audio and recording devices. To change the volume level, simply drag the sliders up or down.




Step 6: Record the screen

When you're ready, click the **REC** button to begin recording.



The capture control panel will change to show recording options. Here you can also keep track of how big the recording is going to be. To pause the recording, click **Pause**. When you're ready to continue, click the **Resume** button. To finish the recording and proceed to saving, click **Stop**. To terminate and delete the recording, click **Cancel**.

[Learn more](#)



Step 7: Save the video

After you end the recording, you can preview the result and choose how you want to save the captured video.

Click the '**Save as**' list and select the format you want to save the video in.

To save as a video format


Click **Video and Audio** at the top of the list and select the necessary format and resolution.

To save for watching on a device

Click **Devices** at the top of the list. Find your device's manufacturer and click on it, and then select the device's model. This will save the video in a format that is guaranteed to be supported by the selected device.

Finally, click **Save** to start processing the video.

[Learn more about saving video](#)




Capturing online video

This manual describes how to capture videos from YouTube. You can also follow the same steps to capture video from other video sharing websites, webinars, sports broadcasts and any other online video.

Step 1: Launch the Screen Capture module

Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.



Step 2: Choose video quality


Many video streaming websites, including YouTube, allow you to select the quality for playing back the video. For the best results, choose the highest available video quality and, if possible, allow the video to load fully before starting capture.

Step 3: Define the capture area

In the **Select Capture Area** section, open the list of pre-defined capture area sizes and choose one from the **YouTube** section:

640x360 – default YouTube player size

854x480 – extended theatrical mode size. You can toggle sizes by clicking the **Theatrical mode**  button in the YouTube player.

The capture area frame will be set to the selected size. Then, place the frame over the YouTube player so that the player's control panel is outside the frame by dragging the frame by the orange position icon .


If you want to capture a fullscreen video, open the list of pre-defined sizes and choose the option under **Fullscreen**. If you have more than one monitor, you will be able to choose which one to use for capturing video.




You can find out more about setting up the capture area [here](#).

Step 4: Choose an audio source

On the capture settings panel, click the **System Sound** button to enable capturing sounds from programs and your system, including the online video player.




Make sure that other sound sources on your computer (for example, videos, streaming music, and ads in other browser tabs, audio players) are muted or disabled to avoid capturing unnecessary sounds. Next, to further reduce noise, we recommend that you disable capturing audio from external devices.




If your computer is running Windows XP, please refer to **Troubleshooting** in the [Recording Audio](#) section for capturing system sounds.

Step 5: Set up mouse visibility


Click the cursor icon  to display the mouse cursor settings panel. To hide the cursor during recording, disable the **Show cursor** option. [Learn more about additional capture options](#)

Step 6: Start recording

Make sure that the window with the video player is in the foreground of your desktop. If you've selected the fullscreen capture mode, don't forget to enable fullscreen playback in the player as well. When you're ready, click the **REC** button or use the start capture hotkey to begin recording. The Movavi Screen Capture control panel will switch to recording mode.




During capture, you can temporarily pause the capturing process. If you're capturing in fullscreen mode, the control panel will be minimized to the system tray. In that case, you can click the Movavi Screen Capture icon in the tray to pause or stop capture, or use the [hot keys](#).



Step 7: Save your video


To finish recording and proceed to saving your video, click the **Stop** button or press the **F10** key (the default stop capture shortcut, your [keyboard shortcut settings](#) may be different). The player window will appear.



In the **Save as** list, choose a format you'd like to save the video in and click **Save**. Your video will be ready in a few minutes. [Learn more about saving captured videos](#)


Capturing Skype calls

When you record audio or video calls using Skype or a similar program, it is important that you record both ends of the conversation. To do that, you will need to record input from your microphone or webcam, as well as the audio from your speakers. Follow the steps below to record Skype calls with audio.




Step 1: Launch the Screen Capture module

Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.




Step 2: Select audio sources

- Click the **System Sound** button to enable capturing the sounds that you hear in your speakers, including your Skype interlocutor.
- Click the microphone icon to enable capturing audio from external devices.
- Open the list beneath the microphone icon and select your microphone or another device that will capture your voice.



Step 3: Set up the capture area


Adjust the size of the [Capture Area](#) to the call window. To do that, click the crosshair button in the left part of the window, and then click and drag your mouse from one corner of the Skype call area to another. When you release the mouse button, the Capture Area will have the same size and position as your Skype window. *You can find more information on how to set the size and position of the Capture Area in the [Defining the Capture Area](#) section.*



Step 4: Call and record

Now that everything is set it's time to make that call!

Click the orange **REC** button to begin recording your call. You will be given a five-second countdown to prepare. If you want, you can disable the countdown window in [General Preferences](#).



Step 5: End call and save

When you're done, click **Stop** in the main Movavi Screen Capture window or press **F10** to finish capturing and proceed to [saving the video](#). You can change the Stop Capture hotkey in **Preferences** under [Keyboard Shortcuts](#).

movavi

Recording [00:00:03 / 872.8 KB]



Duration

00:01:41

Size on Disk:

Recorded: 4.2 MB

Left on Disk: 16.8 GB

✕

Cancel

⏸

Pause

■


Stop

Don't forget to [save the captured video!](#)

Capturing video from players

Step 1: Launch the Screen Capture module

Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.




Step 2: Set up the capture area.

For capturing videos playing in video player applications, it is best if you capture the video as close to its original size as possible. That is, if the video you want to capture has a resolution of 1280x720 pixels, we recommend that you set the capture area to the same size. Most video players have a Zoom option, where you can set the zoom level to 100% or 1:1. If the video is larger than your screen size, you can set the capture area to record the entire screen and then play the video in full screen mode.

To set a fullscreen capture area:


In the **Select Capture Area** section, open the list of pre-defined capture area sizes and select the option under **Fullscreen**. If you have more than one monitor, you can choose which monitor to use for fullscreen capturing.



To capture a player window:

Click the crosshair button in the **Select Capture Area** section to enable smart capture area selection. The screen will dim slightly. Then, draw the capture area *inside* the player, so that the player's window is completely outside the frame. When you release the mouse button, this rectangle will be set as your capture area.


[Learn more about the capture area](#)



Step 3: Set up the sound


When you want to record audio from applications, you will need to enable the System Sound option. Click the speaker icon in the Movavi Screen Capture Studio control panel window to enable capturing sound from players and other programs. As this allows Movavi Screen Capture Studio to record *all* system sounds, make sure to disable sound alerts in other applications to avoid unwanted noise in your video.

[Learn more about sound recording](#)



Step 4: Start Recording

To begin recording, click the red **REC** button or use your **Start\Stop capture** shortcut.




If you want to capture a fullscreen video:

1. If you don't remember your start and stop capture hot keys, open the **Preferences** window, and review them or set different ones in the **Keyboard Shortcuts** tab. Don't forget to close the preferences window before starting playback.
2. In your player, switch to fullscreen mode and launch playback
3. To begin recording, press your **Start\Stop capture** keyboard shortcut.


When you want to end capture, click the **Stop** button or use the **Start\Stop capture** shortcut again and proceed to saving your video.

[Learn more about recording videos](#)



Step 5: Save the Video

After you've finished capturing the video, you can preview the result in the player and save the video. If you want to trim the video, move the triangle markers on the progress bar towards the center. Open the list under **Save as** and choose the format you want to save your video in. You can also prepare the video for viewing on mobile devices or sharing online. When you've selected a format, click **Save** to begin processing the video, or click **Edit** to open in a new Video Editor project. [Learn more about saving captured videos](#)



Troubleshooting:

Some video player programs have video output settings that prevent capturing video and taking screenshots. If you are having trouble recording video from any of the following players, follow the steps to change the player's settings and enable video capturing.

Capturing video from VLC (VideoLan Media Player)

- (for Windows XP users)*
1. In VLC player, open the Tools menu and choose Preferences.
 2. Switch to the Video tab (in Simple mode)
 3. In the **Display** section, find the **Output** list. If **DirectX (DirectDraw) video output** is selected, try using a different output mode.

Capturing video from Media Player Classic

- (for Windows XP users)*
1. In Media Player Classic, open the **View** menu and select **Options**.
 2. Go to the **Playback > Output** section in the tree on the left.
 3. Find the **DirectShow Video** option. Here, you can choose from a list of video renderers that will affect how the player displays video on your screen. If the **Overlay Mixer Renderer** is selected, select any other renderer from this list.
 4. Click **OK** to accept the changes.


Capturing video from Windows Media Player

- (for Windows XP users)*
1. In the main player menu, open the **Tools** menu and select **Options**.
 2. In the **Options** window, switch to the **Performance** tab.
 3. Click the **Advanced** button.
 4. In the **Video Acceleration** section, find the **Use overlays** option and deselect it.
 5. Click **OK** to accept the changes.

Making a video tutorial


Step 1: Launch the Screen Capture module

Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.



Step 2: Record your screen

1. In the Movavi Screen Capture window, select the area of the screen that you want to record. [Learn more](#)
2. Choose which audio that you want to record: system audio to record sound you can hear from your speakers or microphone to record your voice, and adjust audio and microphone volume. [Learn more](#)
3. Click the mouse cursor icon on the control panel and set up mouse cursor highlighting. This will help you bring attention to your actions on screen as you record the tutorial. [Learn more](#)
4. Click **REC** to start recording. When you're done, click **Stop** to proceed.



Learn more: [Capture area](#) | [Sound](#) | [Mouse cursor effects](#)

Step 3: Add the video to the Editor


1. After you've captured your screen, click the **Edit** button to open the captured clip in the Editor. You will be asked to choose an aspect ratio for your project. [Editing captured files](#) | [Setting up a project](#)
2. In the Editor, click **Add Media Files** if you want to add more clips to your project.

Learn more: [Editing the captured video](#) | [New project setup](#) | [Adding media files](#)




Step 4: Cut the video

To cut the captured video, select the clip on the Timeline, place the position marker where you want to cut the clip, and click the scissors button on the toolbar. [Cutting video](#)



Step 5: (Optional) Record and edit audio

- To record an audio voice-over:
1. On the Timeline, place the position marker to where you want the audio to start.
 2. Click the microphone button on the toolbar to open recording options.
 3. Select your microphone under **Audio device**, set up the volume and click **Start Recording**. When you're done, click **Stop Recording**, and you can find your voice-over as an audio clip on the Timeline.
- [Learn more about recording Audio tracks](#)




To manage the volume for any clip, select it on the Timeline and open the **Tools** tab. There, set the **Volume** slider to the necessary level for this clip.


[Learn more about volume levels](#)

Step 6: (Optional) Record video from a webcam

- Many video tutorials and webinars also have the author's webcam video in the corner. Adding your own webcam video is easy: first, record the video and then insert it as an overlay.
1. In the Editor, click the **Record Video** button on the **Import** tab.
 2. The video recording module will open. There, choose your webcam under **Video capture device**, choose a microphone under **Audio capture device**, and then click **Start Capture**.
 3. When you're done recording, click **Stop Capture**, and then **Back to editing** to add the video you've just recorded to the Timeline.
- [Learn more about recording video](#)



4. The recording will appear at the end of the video track of the Timeline. To create an overlay, select the webcam clip and drag it up, towards the top of the Timeline and place it onto the **overlay track**. The video will now appear in a small part of the frame over the main video track.
 5. To change the overlay placement, double-click the overlay clip. Now, you can move and resize the overlay in the player. Click **Apply** on the options panel above the player to accept the changes. Now you have both your captured screen and webcam in the same video.
- [Learn more about overlays](#)



Step 7: (Optional) Highlight objects

In addition to highlighting the mouse cursor, you can bring attention to parts of the screen using the zoom and highlight tools.

- 1. If you have a long recording but you only want to zoom or highlight a part of its length, cut this part into a separate clip and select it.
- 2. Open the **Tools** tab without deselecting the clip. Here, find the **Zoom** and **Highlight and Conceal** tools.
- 3. To zoom in on a clip, select one of the Zoom modes. Then, in the player, select the part of the screen that you want to enlarge and click **Apply** in the Tools tab.
- 4. To highlight a part of the screen, select Highlight inside the **Highlight and Conceal** tool. Then, use the frame in the player to select the part of the screen you want to highlight and click **Apply** in the **Tools** tab.

Learn more: [Cutting video](#) | [Editing tools](#)

Step 8: Export the video

Now that you're done with your tutorial it's time to save it in a format that everyone can enjoy.

- 1. Click the **Export** button to open the exporting options.
 - 2. In the Export window, select a video format that you want to use and choose a folder to save the video to.
 - 3. Click **Start** to begin exporting the video. This may take a few minutes.
- [Learn more about exporting](#)


Making a movie

Jump to:

[Creating project](#) | [Adding files](#) | [Cutting clips](#) | [Editing clips](#) | [Filters](#) | [Titles](#) | [Transitions](#) | [Saving the video](#)

Step 1: Open the Video Editor

Open Movavi Screen Capture Studio and click **Edit Video** to launch the video editing module.



Step 2: Create a new project

When you open Movavi Video Editor, you will be asked to choose an aspect ratio for your new movie. Choose an aspect ratio closest to that of the videos and photos you intend on using. You will be able to change this later.


[Learn more about projects and aspect ratio](#)



Step 3: Add videos, images and music


On the **Import** tab of the Video Editor, click **Add Media Files** to choose the video, audio, and image files you'll be using.

Learn more: [Adding files](#) | [Recording video](#) | [Recording audio](#)



When you open the files, they will be placed on the Timeline: the videos and photos on the video track, and the audio clips on the audio track. To rearrange the clips, simply drag them to the necessary position with the mouse.

Learn more: [Using the Timeline](#) | [Working with video and images](#) | [Working with audio](#)




Step 4: Cut videos

1. Select the clip that you want to split*.
2. Move the position marker onto the moment where you want to cut the clip. You can move the position marker both in the player or on the Timeline.
3. Click the scissors button on the toolbar to split the video into two parts.


Learn more: [Cutting video](#) | [Cutting audio](#)

* Note that if you select a video clip, its audio track will also be cut, unless you move it to a separate audio track. [Learn how to work with audio on the Timeline](#)





Step 5: Edit and enhance clips


Select the clip you want to edit, and click the **Tools** button on the left to see clip editing options. Here, you can edit each clip's speed and volume, as well as rotate, crop, and adjust the videos.



Rotating clips:

1. Click **Rotate and Flip** to open the rotation options.
2. Click the arrows to rotate the selected clip 90° clockwise  or counterclockwise .


[Learn more about rotating clips](#)



Enhancing photos and videos:

Auto adjustments can help you enhance your videos and photos in one click, making them more vibrant.


- 1. On the **Tools** tab, click **Color Adjustments** to open the adjustments for the selected clip.
 - 2. Select the auto adjustments that you want to use. **Magic Enhance** will instantly fix the clip's brightness and contrast. These enhancements are fully automatic.
- [Learn more about enhancements](#)



Step 6: Add Filters


Filters can help you change the colors in your photos and videos or add an artistic touch. To apply a filter:

- 1. Click the **Filters** button to open the filter library. To preview a filter effect, click on its thumbnail.
 - 2. Drag the filter's thumbnail down onto a clip on the Timeline to apply it. A star icon will appear on the clip.
- [Learn more about filters](#)



Step 7: Add text titles


- 1. Click the **Titles** button to open the titles collection. To preview a title style, click on its thumbnail.
 - 2. Drag the titles you like onto the *top* of the Timeline. The title track will appear. Place the titles where you want them to appear relative to the other clips.
 - 3. To change the text and edit the title style, double-click the titles clip you've just placed. The title properties panel will appear in the player, where you can edit and move the text.
- [Learn more about adding titles](#)



Step 8: Add transitions

- 1. Switch to the **Transitions** tab, where you can choose animations to smoothly join the clips.
- 2. Drag-and-drop a transition icon in between two clips on the Timeline.

[Learn more about transitions](#)




Step 9: Export the finished video

Make sure to save your work once in a while: choose **Save** from the **File** menu to save the slideshow project so that you can access it later.

When you're done with the slideshow, click the **Export** button to open the exporting options. In the **Export** window, choose a format you want to save the video in, and name your slideshow. Finally, click **Start** to begin processing the video. Your slideshow will be ready in a few minutes.

[Learn more about saving your video](#)



Having trouble with something? E-mail us and we'll help you out! Our e-mail: support@movavi.com

Recording audio

Step 1: Connect a microphone

Connect a microphone to your computer and make sure that it is recognized by the system.

Step 2: Open the audio recording module

Open the Movavi Screen Capture Studio launcher and click **Record audio**. The audio recording module will open in a separate window.




Step 3: Set up audio capture

In the **Audio capture device** box, choose the microphone or whichever device you want to use for recording sound. To record audio that is playing on your computer*, choose 'Stereo Mix' or 'Speakers'.

** Depending on the model of your audio card, this option may be named differently. Some device manufacturers do not include a system audio recording option.*

In the **Saving captured files** section, you can choose a template for naming the captured files. To do that, open the **File renaming box** and choose **date** or **free text**. Then, fill in the template details and the recordings will all be named after this template.


Under **Save files to**, specify the folder where you want to save the recordings. Click the folder icon next to the box to browse for the folder you need.



Step 4: Record

Click **Start Capture** to begin recording. As you record sound, you can see the frequencies reflected as color bars in the center. When you're done, click **Stop Capture**. If you need to record more audio clips, simply repeat this step.

The audio files will be saved to the folder specified in the '**Save files to**' box. To open this folder, click the **View saved files** button.




Using Screen Capture

Movavi Screen Capture Studio consists of two functional applications: the Screen Capture module and the Video Editor. The **Screen Capture** module lets you record any part of the screen and save the resulting video as a common media format or continue to edit it in the Video Editor. When you open Movavi Screen Capture, you will see a control panel window, where you can set up your capture preferences, and an orange frame which allows you to select which part of the screen you want to record.



Step 1: Launch Screen Capture

To launch the Screen Capture module, open Movavi Screen Capture Studio and click **Capture Screen**.



Step 2: Set up the capture area

Choose a full screen capture mode or click the crosshairs button to select a window.

Step 4: Extras

Use extra options to enrich your recording.

[Schedule events](#)

[Highlight cursor](#)

[Record keystrokes](#)

Step 3: Set up sound

Choose whether you want to record audio from your speakers or the microphone.

Step 5: Record screen

Start the recording by clicking the REC button.

Press F8 to take a snapshot.

Press F10 to start and stop the recording.

Press F9 to pause the recording.

Step 6: Save the result

Learn how to save your recording to a common media format.

[Edit captured videos](#)

[Reduce output size](#)


Capture area

The orange frame defines which part of your screen will be visible in your screen recording.

Record full screen

To record a full screen video, open the list on the control panel and select your display.

Note: if you have enabled the capture control panel, it will be visible on full-screen recordings. You can disable it in the [Screen Capture Preferences](#). Also, the main Movavi Screen Capture window will hide, but you can use keyboard shortcuts or the tray icon to begin recording.



Record a window


Using the smart selection tool, you can select any window and the frame will be automatically set to its size and position.

1. Click the crosshair button on the Movavi Screen Capture window.
2. The screen will dim slightly. Move your mouse pointer over to the window you want to capture and click on it. An orange frame should appear around the window. If you move the window, the capture frame will also follow.



Record a YouTube player


1. Open the list on the Movavi Screen Capture window. There, find the **YouTube** section and select the size you need. The smaller size is the regular player size, while the larger size is YouTube's Theatrical Mode.

2. Click and drag the orange square  in the center of the capture frame to move it over the YouTube player.

[Learn more about capturing YouTube](#)

Record a standard size

You can select from any of the standard or widescreen sizes that match common screen resolutions and windows.

1. On the Movavi Screen Capture window, open the list under '**Select Capture Area**'.
2. Select a size that fits your needs.
3. Click and drag the orange square  in the center of the capture frame and move it to the necessary position.

Custom frame size

You can set virtually any frame size for your recording using a number of ways:

Draw the capture frame

1. Click the crosshairs button on the Movavi Screen Capture window to enter smart selection mode.
2. The screen will dim slightly. Click and drag diagonally to draw the capture frame rectangle.




Exact size

If you want to set a specific size, enter the width and height into the boxes on the Movavi Screen Capture window:



Drag the edges

Move your mouse pointer over the edge of the capture frame, and click-and-drag at them to change the size of the frame.



Moving the capture frame

To move the capture frame, click and drag at the orange square in the center of the capture frame to move it across the screen.



Sound

Movavi Screen Capture can capture sound from a variety of sources.

System Audio

To capture audio from applications, music, videos, and other system audio, click the **System Audio** button to enable capturing sound from these sources.




Recording Devices

If you want to record audio from external devices:

1. Click the microphone button to enable device capturing.
2. Select the necessary device from the list.




If you want to record both system audio and an external device (for example, to capture Skype calls), simply select both options.



Audio volume

Before you start recording, you can adjust the volume levels both for the system audio and your microphone. To change the volume, simply drag the sliders up or down.

This may be useful for recording tutorials with a voice-over to make sure that the microphone is always louder than the system audio.



Troubleshooting

Capturing system sound on Windows XP

Windows XP does not support recording from multiple audio sources: that is, you will not be able to easily capture system sound and an external audio device. However, you can still capture system sound separately:

1. Click the microphone button to enable recording from audio devices.
2. Select **Stereo Mix**.

See also:

- [Recording only audio](#)
- [Recording Skype calls](#)


Scheduling

You can use Movavi Screen Capture to record your screen at any time.


To set a time limit

If you want the recording to end automatically after a certain period of time:

1. Click the clock icon to open the capture time options.




2. Select the '**Stop capture after**' option.
3. Enter the time after which the recording should end (*hours:minutes:seconds*).




To schedule a recording

You can record anything on your screen without even being at your computer, as long as you know when to start and end the recording.

1. Click the clock icon to open the capture time options.



2. Select the '**Schedule recording**' option.
3. Next to **Start time**, enter the date and time when the recording should start.
4. Next to '**Stop capture after**', enter the time after which the recording will automatically end (*hours:minutes:seconds*).



When the time comes, the recording will begin automatically. Before that, don't forget to set up the [capture area](#) and [sound](#). You do not need to press the 'REC' button for the recording to begin, however, please note that Movavi Screen Capture will need to be running at the specified time. To ensure that, you can enable autostart in the [Preferences](#).

Please note that if you haven't yet activated the program, the maximum capture time is two minutes for each video. To learn more about activating Movavi Screen Capture, see the [Activating Software](#) section.

If you are starting a lengthy recording, make sure that you have enough free disk space for saving the temporary recording files.

Highlighting events

If you're making a video tutorial, it can be very helpful to draw attention to onscreen actions.

Highlighting the cursor

To show mouse actions in your video, you can choose to display a standard mouse, highlight the cursor, or use an effect for mouse clicks.

[How to highlight the cursor](#)



Highlighted mouse and left click

Hiding the cursor


If you don't want to see the cursor on your recording, you can hide it so that it won't show up on the finished video even if you move it over the capture area.

[How to hide the cursor](#)

Showing the keystrokes

If you're using keyboard shortcuts, you can display every key and key combination that you press on your video.

[How to show keystrokes](#)



The key combination will appear at the bottom of the video

Mouse cursor effects

Using mouse effects, you can use the mouse as a pointer and show your viewers where to click.

Show the mouse cursor

1. Click the mouse icon on the Movavi Screen Capture control panel to open the cursor options:
2. In the **Cursor options** box, select the **Show cursor** option.

The cursor will now appear on your videos.

Highlight the mouse

1. Click the mouse icon on the Movavi Screen Capture control panel to open the cursor options:
2. In the Cursor options box, select the **Show cursor** option if it is not yet enabled.
3. Select the **Highlight cursor** option.
4. To change the highlight color, click the square next to 'Highlight cursor' to open the palette and select a new color.
5. To change the diameter of the highlight, use the **Size** slider.

Highlight clicks

1. Click the mouse icon on the Movavi Screen Capture control panel to open the cursor options:
2. In the Cursor options box, select the **Show cursor** option if it is not yet enabled.
3. Select the **Highlight clicks** option.
4. To the right of the 'Highlight clicks' option, you will see two color squares. Click the left or right square to change the color for the left or right mouse button respectively.


Use a click sound

1. Click the mouse icon on the Movavi Screen Capture control panel to open the cursor options:
2. In the **Cursor options** box, select the **Show cursor** option if it is not yet enabled.
3. Select the **Mouse click sound** option.
4. If you want to use your own sound effect, open the list and choose Add sound. Then, select the sound file that you want to use.

Hide the mouse cursor

If you don't want to see the mouse cursor on your video:


1. Click the mouse icon on the Movavi Screen Capture control panel to open the cursor options:
2. In the Cursor options box, disable the **Show cursor** option. The cursor will now be transparent in your videos, even though you will be able to see it on your screen.





Recording keystrokes

If you're making a tutorial that uses keyboard shortcuts, it's helpful to display them on screen for your viewers. Enable keystroke recording to show the keys you pressed at the bottom of the video.

To enable keystroke recording:

1. On the control panel, click the keyboard icon: . The keyboard options panel will appear.
2. In the keystroke recording options panel, select one of the options:
 - **Keyboard shortcuts only** — only key combinations such as *Ctrl+C* or *Shift+Control+Esc* will be shown on screen. Letters and keys that do not cause an action will not be displayed.
 - **All keystrokes** — each key you press will appear on screen, including letters and numbers.

Once enabled, the keystroke recording icon should turn orange .




To turn off keystroke recording, click the keyboard button once again and disable the options.

Tip: avoid entering any passwords or other sensitive information while you're recording a video with keystroke recording: if you share the video, your viewers will be able to see each character you type.


Starting the recording

Begin recording

To begin recording screen activity, do any of the following:



- Click the **REC** button on the control panel.
- Use the start recording keyboard shortcut (**F10** by default)
- In the system tray, right-click on the Movavi Screen Capture icon  and choose **Start Recording**.

You will be given a 5-second countdown before recording begins.



Pause recording


To pause recording, do any of the following:

- Click the **Pause** button on the control panel.
- Click the **Pause** button on the orange panel at the top of the capture frame: 
- Use the pause capture keyboard shortcut (**F9** by default)
- In the system tray, right-click the Movavi Screen Capture icon  and choose **Pause**.

When you're ready to resume the recording, the **Resume** button will be in the same location as the Pause button.

To take a screenshot



To save a snapshot of the capture area, do any of the following:

- Click the screenshot button on the orange panel at the top of the capture frame: 
- Press the screenshot keyboard shortcut (**F8** by default).

Screenshots are saved to the folder specified in the [preferences](#). By default, it will be the `\Videos\Movavi Screen Capture Studio\Screenshots` folder of your user directory.


Stop recording

When you're ready to finish the recording, do any of the following:

- Click the **Stop** button on the control panel.
- Click the **Stop** button on the orange panel at the top of the capture frame: 
- Use the stop recording keyboard shortcut (**F10** by default)
- In the system tray, right-click on the Movavi Screen Capture icon  and choose **Stop Recording**.

The recording will end, and you can proceed to [saving the output video](#).

If you want to terminate the recording *without* saving the video and delete the temporary recording file, click **Cancel** on the control panel.



Troubleshooting:

Windows style changes when I start recording

If you have a Windows Aero theme (Windows Vista, Windows 7), disabling the transparency effects will free more resources and your computer will run faster during capture. The Aero theme will return once you have finished capture. To disable this, open the [Preferences](#) and turn off the '**Disable Aero theme during capture**' option in Video preferences.

Capture doesn't start immediately

By default, you will see a five-second countdown after you press the REC button and before the recording begins. You can use this time to prepare for recording. If you want the recording to start immediately, open the [Preferences](#) and disable the '**Show countdown**' option.

An orange panel appears on my recording

During recording, you can use the orange panel on top of the capture frame to take screenshots, pause or stop recording, and keep track of the recording process. If you don't want this panel to appear on your videos, open the [Preferences](#) and disable the '**Show capture control panel during recording**' option.

Saving the captured video

When you end the recording, you will see a player with the captured video which you can preview before saving. If you want to edit the video first, click the **Edit** button to open the video in the Video Editor application.
[How to send captured videos to the Editor](#)

Step 1: Choose a capture format

To save as a video file:

1. Click the '**Save as**' box to open the list of output formats.
2. At the top of the list, click **Video and audio**.
3. Find the necessary format in the list and click on it to see more options.
4. Choose a video codec and resolution that you want to save the video with. To save the video without changing the resolution, choose the item marked with '*Same as input*'.


[How to choose a resolution?](#)

To save the video for a device:


1. Click the '**Save as**' box to open the list of output formats.
 2. At the top of the list, click **Devices**.
 3. Find your device's manufacturer in the list and click on it to see more options.
 4. Find your device's model and click on it to select it as the output format.
- The format, resolution, and other media properties will be selected automatically to ensure compatibility with the selected device.

To save only audio:

1. Click the '**Save as**' box to open the list of output formats.




2. At the top of the list, click **Video and audio**.
3. Scroll down to find audio formats at the bottom of the list.
4. Find the necessary audio format in the list and click on it to see more options.
5. Choose the item with the bitrate that you want. Bitrate affects how much audio quality will be retained after saving. To save with the original audio quality, choose the item marked with '*Same as input*'.



Advanced settings

If you need to save the video with specific properties, click the cogwheel button  next to the 'Save as' box to manually edit the media properties for video and audio.

Step 2: (Optional) Trim the video

If you have unwanted footage at the beginning or at the end of your video, you can trim it using the triangle markers  on the player's progress bar. Click a marker and drag it towards the center of the progress bar to trim the video. After this, the fragments outside the markers will not be saved.




Step 3: (Optional) Compress the video

At the bottom of the player window, you can see the estimated size of the output video. If you want to compress the video to a smaller file size:

- 1. Click the **estimated file size** to open compression options.
- 2. In the file size box, drag the **Quality** slider left to decrease quality and file size. Keep an eye on the quality in the brackets to make sure you don't set it too low.
- 3. Click **Apply**.

[Learn more about compressing the video](#)



Step 4: (Optional) Export the video


If you want to add the video to your iTunes library or share it on the web immediately after saving, you can do it using the export options when saving the video.

- Add to iTunes** – select this option to add the captured video to your iTunes media library. *You will need to have iTunes 6.0 and above installed on your computer to use this feature. You can get the latest version of iTunes from the official Apple page [here](#).*
- Upload to** – Click this option to open the list of available services and select the sites or hosting that you want to upload the video to. Once saving is complete, the Share Online module will open, where you can prepare your files for uploading.

[Learn more about uploading videos via Share Online](#)

Step 5: Save the video

After you have selected the output format, click **Save** to start processing the video.





Choosing a resolution

How to keep the original resolution


If you open the list of presets under **Save as**, you will see that some presets are marked with a specific resolution size, such as 720p or 1080p. While these resolution sizes can help you easily scale your video if you've captured it using one of the standard sizes, they may not be as effective if you've captured it using a custom capture area size.

To save your captured video with the original resolution, you will need to either choose a format from the **General Video** group (located under Video and audio formats), or choose a format preset titled '**Same as input**'.




How to avoid black bars


When you save or convert videos with a different aspect ratio (the ratio of the video's width to its height), the output file may come out with black bars around it. This happens because a video of one size needs to be fit inside the new frame without deforming the image itself. Just imaging fitting a rectangle inside a square and vide versa.



To solve this problem, you will need to either save the video without changing the resolution (see above), or change how you want the video to be placed inside the frame. To do that,

1. Choose a resolution size that you want in the preset list. To avoid losing quality, it should closely match the size of the original video either in width or in height.
2. Click the cogwheel button  next to the Save as list to open settings for the chosen preset.
3. Find the **Resize method** list and open it. Here, you can choose the way your video will be fit inside the selected frame size.
 - Letterbox** is the default method that saves videos with the least distortion, but may add black bars in the region around the video.
 - Stretch** will literally stretch the original video to fill the whole screen, however, this may lead to visual distortions.
 - Crop** will scale the video to fit the entire frame on the short side, cropping anything that does not fit. While some parts of the video will be cropped, the objects inside the video will maintain their proportions.
 - Auto** uses a combination of both stretch and crop methods.

Choose the most appropriate resize method depending on the content of your screencast. You can refer to the image in the **Settings** window for a preview. Click **OK** to accept the changes and close the window.





Small resolution videos

For best results, choose a resolution size less than or equal to that of the capture area you used. Due to video compression restrictions, If you save your video to a larger resolution, you will not get better quality, but the file size will be considerably larger.

Setting a custom resolution

To set a resolution that is not included in the list of presets:

1. Choose a preset with the necessary format. You can choose any resolution at this point.
2. Next to the **Save as** list, click the cogwheel button  to open the settings for the chosen preset.
3. Enter the necessary frame size in the **Width** and **Height** boxes. Note the link button to the right of the **Height** box: . By default, the width and height you enter will be adjusted to fit the selected proportions. Click the link button to disable proportion constraining.

Please note that if you want to savmule videos for a mobile device, some devices may not support the new custom resolution. For best compatibility, use the same aspect ratio and a smaller frame size than that of the device preset.

MP4 Settings

Preset: Google Nexus 10

Save as

Delete

Video

Audio

Codec

H.264

Frame size

720 x 576

Width (px)

720

x

576

Height (px)

Resize quality

Good (Fast)

Resize method

Letter Box

Bitrate type

Auto

Frame rate



Auto

Bitrate (kbps)

Show Advanced


OK

Cancel



Reducing output size

Long recordings with a large capture area size may take up a lot of disk space. When saving the video, you can see the estimated file size at the bottom of the player window. This shows approximately how large the ouput video will be after saving with the currently selected format.



Here are some things you can do to reduce the file size:

Use a smaller resolution

When you select an output format, choose a resolution that's slightly lower than the original video size. The resolution is listed next to each output preset:




For example, changing the resolution from 1080p to 720p can reduce the video up to half the size. However, note that resolution affects video quality, so setting a resolution too low can reduce its quality.

Compress the video

When saving the video, you can reduce the quality in order to achieve a smaller file size.

1. Click on the estimated file size at the bottom of the player window to open compression options.
2. Drag the **Quality** slider to the left to reduce the video's bitrate. Bitrate is the amount of data in each second of the video. A slightly lower bitrate may not even be visible to the eye, but it can significantly reduce the file size. The text in brackets will tell you if you've set the quality too low.
3. Click **Apply** to accept the changes.



Publishing videos online


You can upload the finished videos straight to social networks and file hosting folders using an additional module – Movavi Share Online. Follow the steps below if you want to learn to upload your captured videos online.

Before you start:

If this is your first time uploading videos from Movavi Screen Capture Studio, you will need to download and install an additional module (it's free!). [Click here](#) to download the installation file and then follow the instructions to install the software.

Step 1: Choose sites to upload

Before you save a video, click the **Upload to** option at the bottom of the player window and select the web sites or services that you want to upload the video to. Please note that you will need to have an active account on the selected websites in order to upload videos and that some services impose a length restriction.



Step 2: Save the video

Click the **Save** button to begin video processing. After the output video is ready, the Share Online module will open with your file already in the upload queue.


If you are using Share Online for the first time, you may be asked to provide your login details for the selected services. The information you provide will be used only for authorization with the website so that Share Online can upload videos on your behalf.

Step 3: Fill in the details

In the file list on the left, click your Screen Capture Project file to select it. The right-hand pane will display several information fields for the selected video. Fill in the title, description, tags, etc. This will help the video sharing service to categorize your video. Some services also allow you to set privacy settings.

Step 4: Upload the video

Click the **Upload** button in the bottom right-hand corner to begin uploading the video.



Editing the captured video

After you've captured your screen, you can immediately send the video to Movavi Video Editor. To do that, click the **Edit** button at the bottom of the player window:



Movavi Video Editor will open, and the video will be placed on the Timeline.


- See also:**
- [Cutting video in the Editor](#)
 - [Editing tools](#)
 - [Saving video in the Editor](#)

Recording and saving audio

Movavi Screen Capture can help you not only record any screen activity, but it can also function as a sound recorder to record online music, radio broadcasts, and voice input.

Step 1: Launch the Screen Capture module


Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.



Step 2: Set up Audio

Naturally, if you want to record an audio file, you'll need to enable audio recording.

- To capture audio **from your computer**, make sure that the **System Audio** option is enabled.
- To capture audio from a **microphone** or an external device, click the microphone icon and choose the device you will be using for recording.
- To capture **Skype** audio, you'll need both options enabled in order to capture the audio from the other end of the call as well your own microphone input.



Here, both System Audio and device recording are enabled

Troubleshooting audio:

If you don't see the device you want to use in the list, it may be disconnected or disabled in system settings.

1. Right-click the sound icon in the Windows notification area and choose **Recording Devices** from the pop-up menu. The Sound settings window will open.
2. In the **Recording Devices** window, look for the necessary device in the list. If it is detected and enabled in your system, there should be a green checkmark beside it.
3. If you cannot find the device in the list, right-click anywhere in the list and make sure that the options **Show Disabled Devices** and **Show Disconnected Devices** are selected.
4. If the device is listed as **Not Plugged In**, try plugging in the device again.
5. If the device is listed as **Disabled**, right-click the device and choose **Enable**.

Step 3: Set up Video

No video:


If you'll only be recording the audio, or if there's no video at all, we recommend that you make the capture area smaller, so that video recording does not unnecessarily take up your disk space. To do that, you can resize the capture area with your mouse, or enter smaller dimensions in the Movavi Screen Capture window. You can set the capture area to as small as 16x16 pixels.

With video:

If you'll also be recording video, move the capture area over the video:

- Drag at the orange square in the center of the capture area to move the frame
- Drag at the corners of the frame to resize the capture area.

[More on setting up the capture area](#)



Step 4: Record

Click the **REC** button to begin recording. You will be given a 5-second countdown to start the audio playback (don't worry you will be able to trim the file later if you accidentally record some silence). When you're done recording, click the **Stop** button.



Step 5: Save Audio

When the recording is finished, you will see a player window, where you can preview and save the recording as an audio file.

Trim the file:

If you've accidentally recorded some unwanted parts, like silence at the beginning or at the end of the file, you can easily trim them before saving the file. At both ends of the progress bar, you will find a pair of triangular trimming markers. These markers control which part of the recording is saved in the output file. Move the triangle markers so that the unwanted parts are outside of them.



Trimming markers

Save the file:

- 1. If you're ready to save the audio file, open the **Save as** list and click the **Video and audio tab** at the top of the list.
- 2. Scroll to the very bottom of the list to find audio formats and choose the format you like. If you're unsure, you can use *.mp3, as it is the most widely supported format.
- 3. Click the **Save** button to start saving the video.




Saving previously captured files

As your record onscreen videos, they are first stored as files with the *.*mscproj* extension. These files are located in the directory you've specified in [File Preferences](#), or in the default *\Videos\Movavi Screen Capture Studio\Projects* folder. You can later open these captured files and save them in the format of your choice.

To open the temporary files:

- 1. In the menu bar, open the **Capture** menu and select **Open Captured File (Ctrl+O)**
- 2. Select the *.*mscproj* file you want and click **Open**. You can now save or convert the video just like after any other capture.




Saving screenshots

You can save snapshots of any area of your screen, including videos playing in various media players.

Taking screenshots before capture:

1. Open Movavi Screen Capture Studio and click **Capture Screen** to launch the screen capture module.
2. Set up the capture area to include the part of your screen you want to take a snapshot of, or click the list of standard resolutions and choose a variant youu need. For more information, please see the [Capture Area](#) section.



3. Take a screenshot:


- Select **Take a Screenshot** in the **Capture menu**
- Or use screenshot shortcut key (F8 by default). You can change it to a custom key or key combination in [preferences](#).

4. In screenshot saving window choose a destination folder for screenshots, choose suitable file type from **Files of type** list and finally click **Save**.

Taking screenshots during capture:

- Select **Take a Screenshot** in the **Capture menu**,
- Or use screenshot shortcut (F8 by default). You can change it to a custom key or key combination in [preferences](#).


After capturing video you will see a number of screenshots taken during capturing at the bottom of the saving window. You can also click on the number to open screenshots folder. The screenshot destination folder can be changed in [preferences](#).



Tip: if the main window is visible inside the orange capture area during capture (for instance, when you capture fullscreen on a one-monitor personal computer), it will be visible on screenshots as well. We advice you to minimize the main window during capture and use shortcut keys for taking screenshots..

Screen Capture preferences


To open the program settings for Movavi Screen Capture for Mac, open the **Capture menu** and select **Preferences**.



The preferences are organized into four categories: [General](#), [Files](#), [Keyboard Shortcuts](#), [Video](#), and [Audio](#).

General preferences


The **General** tab allows you to change the interface language and set the folder where you want the captured files to be stored by default.



- ☒ Select the **Automatically check for updates** option to make sure your Video Converter is always up-to-date. Minor updates are absolutely free (for example, from v.1.3 to v.1.4). For major updates users with purchased Movavi Screen Capture Studio license will get a considerable discount.
- ☒ **Send anonymous usage stats to Movavi** – checking this box will allow Movavi Screen Capture to send usage statistics to our development team, enabling us to fix any bugs you may encounter much faster, as well as add new features that you might be missing. The data sent by Movavi Screen Capture contains no personal information, will not be disclosed to third parties and will be used for software improvement purposes only. You can find more information about usage statistics on our [Movavi Improvement Program](#) page.
- ☒ **Show countdown** – with this option selected, whenever you start capture, recording will not begin right away, rather, you will be shown a 5-second countdown to give you time to prepare.

File preferences


The Files tab of Movavi Screen Capture Studio preferences allows you to manage the folders where you want Movavi Screen Capture Studio to store its files. Click the arrow button next to a folder to set a different location.



Directory for captured files: where your output videos will be saved. After you save a video, this folder will open automatically.

Directory for screenshots: if you take screenshots during capture, they will be saved to this folder.

Directory for temporary files:
When you record screen activity, Movavi Screen Capture Studio first writes your video as a temporary project file with the *.mscproj extension. This file is stored in your **Directory for temporary files** until you [save](#) it as a video or audio file. Besides, you can always [open a project file](#) and resave it in a different format.

By default, the files are stored even after you save the video, in case you want to reuse the temporary file and save it to a different format, however you can delete all temporary files by clicking the trash can icon next to the **Directory for temporary files** .

☒ **Delete temporary video files after conversion** – with this option selected, the temporary files will be deleted immediately after you save the videos. This will help you save disc space, however you will not be able to save the recording in a different format afterwards.

Directory for screenshots: when you take screenshots during capture, they will be saved to this folder.

Default screenshot format: when you take a screenshot, it will be saved with the selected format.

Keyboard shortcuts

The **Keyboard Shortcuts** tab allows you to set your own custom shortcuts for such actions as starting or pausing the capturing process. On the left you can see keyboard shortcuts for every action.

General	Click in the Keyboard Shortcut field and press the key combination that you want to assign to the menu command.	
Files	Start/stop capture:	F10
Keyboard Shortcuts	Pause/resume capture:	F9
Video	Take a screenshot:	F8
Audio	Reset to Default	
OK Cancel		


To change one of the shortcuts:

- 1. Click inside the box with the shortcut you want to change. The box will become blank.
- 2. Simultaneously press on keyboard the keys you want to use as a shortcut to the selected action. The box will now display your custom shortcut.
- 3. Click **OK** to apply the changes. To reset all the keyboard shortcuts to their original state, click the **Reset to Default** button.

In case you forget a shortcut, you can always look it up here in the keyboard shortcut settings.

Video preferences

The **Video** tab contains advanced video settings. If you need your videos in another format, we recommend that you save them in the necessary format after capturing. Please see the [Saving video](#) section for more details.




Codec: the codec which will be used for capturing videos. The H.264 codec is suitable for most video capturing scenarios.

Maximum capture frame rate: like in regular video, the frame rate will define how many frames will be captured each second. A lower frame rate will result in smaller output size, however, the video may not turn out as smooth. The recommended frame rate is 20-30 frames per second.


Output frame size: defines the dimensions of the captured video. 'Full size' means that it will be captured "as-is", while other frame sizes will result in some scaling to fit the captured area into the specified frame.



For example, if you are capturing a 1280x720 screen with a frame size of 480x320, the captured image will need to be scaled down. Likewise, if the area you are capturing is smaller than the output frame size, the video will need to be scaled up, which results in larger file size with no gain in quality.

☒ **Enable SuperSpeed conversion** – the SuperSpeed conversion method allows Movavi Screen Capture Studio to save your recordings much faster if you select presets marked with the green SuperSpeed icon .

Setting custom video preferences allows you to save time if you intend to always capture videos in one format, but some options like a higher frame rate and larger frame size will require more resources. We recommend that you keep the default settings and convert your videos to the necessary format and frame size when [saving](#).

☒ **Enable Intel® hardware acceleration**– if your computer is equipped with one of the latest Intel® processors, the captured videos will save much faster if you select conversion presets marked with the blue Intel icon: .

For Windows 8 and Windows 10 users:

☒ **Use alternative capture mode (not recommended)** - turns on alternative capture method. Enable if errors or crashes occurred during the capturing process. Not recommended when there are no such problems.

For Windows Vista and Windows 7 users:

☒ **Disable Aero theme during capture** – if you are running Windows Vista or Windows 7, the transparency in the 'glass' Aero theme is harder to process and may cause defects in the captured video, especially if you are using a slower computer. With this option enabled, your theme will be switched to the Windows Simplified theme when you begin capturing. Once you stop capture, the original theme will be restored.

For users of Windows 7 and lower:

☒ **Use DirectX for capturing** – try this option if you are experiencing problems capturing some program windows. In Windows 8 and above, the capture method is chosen automatically and this option is unavailable.

Audio preferences

The **Audio** tab allows you to change the preferred audio quality, including the sample rate, number of channels, and bits per second.

General

Files

Keyboard Shortcuts

Video

Audio

Audio quality:


44.1 kHz, stereo, 16-bit

OK

Cancel


Using the Video Editor

Movavi Screen Capture Studio consists of two functional applications: the Screen Capture module and the Video Editor. Using the **Video Editor**, you can edit the captured videos, join them with additional material, add a soundtrack, and even create new movies from scratch.



Step 1: Open the Editor

To launch the Video Editor, open Movavi Screen Capture Studio and click **Edit Video**, or click the **Edit** button in the Screen Capture module after you've captured a video.



Step 2: Add media

Add videos, photos, and music to your video project.

[Open captured videos in the Editor](#)

[Record video](#)

[Record audio](#)

[Arrange files chronologically](#)

Step 4: Join clips with transitions

Drag-and-drop transitions from the Video Editor's extensive collection to join clips with fun animations.

Step 3: Edit video

Edit and enhance the video clips to make your video just the way you like it.

[Cut and split video](#)

[Rotate clips](#)

[Crop the frame](#)

[Apply cool filters](#)

Step 5: Annotate your video

Get your thoughts across with sound and text.

[Record a voice-over](#)

[Add text titles](#)

Step 6: Save your video

Export your project to a common video format.

[Save for devices](#)


[Save for uploading online](#)

New project setup

First of all, you will need to create a new project and select some of its parameters.

Creating a new project

1. Open the **File** menu and choose **New Project**.
2. A dialog box will appear. Here, you can select the parameters of your future movie.
3. Choose an *aspect ratio* for your project by clicking the **16:9** or **4:3** button.
4. Click **OK** to continue with your project.



What is a project?

A project is a file with the *.mepx extension that stores all your work on the movie, including the order of videos on the storyboard, and any other changes you have made while editing the video. Project files can only be opened with Movavi Video Editor or Movavi Slideshow Creator.

What is aspect ratio?

Aspect ratio describes the proportions of the video frame, and is basically the ratio of the video's width to its height. When choosing a project, you can choose between two most common aspect ratios: **16:9** and **4:3**. 16:9 is the most common aspect ratio used for digital videos, especially widescreen movies, while 4:3 is closer to a square, and was used for analog television.



A visual comparison of the two common aspect ratios

Ideally, the project's aspect ratio should match that of the photos and videos you plan to use in your movie. This way, all of the photos will fit inside the frame nicely. If you add files with a different aspect ratio, they may appear to have black bars around them, like so:



Adding 4:3 photos to a 16:9 project and vice versa

You don't have to choose the perfect aspect ratio right away, if you're unsure, you can always change this later in project settings, or fit the images into the selected frame.

- [Learn more about project settings](#)
- [Learn how to get rid of black bars](#)

Advanced settings

If you need to set other parameters, click the **Advanced settings** button in the project window. You will be able to choose the following:

Frame size:

You can use this to choose a set frame size (width and height) of the project. If your photos have a different aspect ratio, you can select Custom and enter the photos' width and height into the boxes below to set their proportions for the whole project.

Resize method:

This affects the way photos and videos are resized to fit the project's frame size. Photos with the same aspect ratio as that of the project will fit in nicely, while others will need to be somehow adjusted in order to avoid black bars on the sides. You can choose one of the following options:

- **Letterbox** - the photos and videos will retain their original proportions, and will be resized to fit inside the frame.
- **Stretch** - the photos and videos will be resized to fit inside the frame as best as possible, and then stretched to fill the remaining space. This allows to fill the entire screen without black bars, but it may distort objects in the photos.
- **Crop** - the photos and videos will be resized in such a way as to fill the entire frame without changing their proportions at the expense of cropping away the edges. This allows to fill the entire screen nicely, but some parts around the edges will not be visible.

Sample rate:

This affects audio quality. The default option, 44100 Hz, is suitable for most projects.

Channels:

This affects the number of channels in the project's audio. You can choose between mono (one channel) and stereo (two channel) sound, but stereo is usually best for most projects.

If you want to change these later, open the project settings.

See also:


[Saving your work](#)
[Project settings](#)
[Exporting your movie](#)

Adding media files

To begin working on your video project, you will first need to add some media files to the Editor.

Open the Import tab

The **Import** tab contains options for opening and creating media. To open it, click the **Import** button in the upper left-hand corner of the Video Editor window.




The *Import* tab is the first one you see when you open Movavi Video Editor.

Adding video, photo, and audio files

If the media you want to use is stored in a file, use the buttons in the **My files** section or drag-and-drop media files straight from Windows Explorer onto the Timeline to add them to the project.

- To add one or several files from a single folder, click **Add Media Files** and choose the files you want to use.
- To add the contents of an entire folder, click **Add Folder** and select the folders you want to import.




Recording video

You can also record video from your webcam, record clips from a TV tuner or import files from a digital camera.

1. Click the **Record Video** button. The Video Capture module will open.
2. In the Video Capture window, set up your video and audio capture devices.
3. Click **Start Capture** to record the video.

When you're done, click **Back to editing** to import the recordings into the project.

[Learn more about recording video](#)



Using stock media

If your project is missing cool footage, music, or backgrounds, use the free stock clips included with the Video Editor.

Sample audio

1. On the **Import** tab, click the **Sample audio** section to open the free stock audio collection.
2. Click on an audio clip to preview it.
3. Once you've picked a clip you like, drag it onto the audio track of the Timeline.

To find more songs for your project, click **Download more** and subscribe to *AudioBlocks.com* — a stock audio bank where you can find thousands of songs, themes and audio samples.

Stock video

1. On the **Import** tab, go to the **Sample video** section to open the free video collection.
2. Click on a clip to preview it.
3. Once you've picked a clip you like, drag it onto the video track of the Timeline.

If you can't find the right clip, click **Download more** and subscribe to [VideoBlocks.com](#) — a stock video collection with thousands of royalty-free videos, footage clips and animations.

Backgrounds


1. On the **Import** tab, go to the **Backgrounds** section to open the free stock background collection.
 2. Pick a background you like and drag it onto the video track of the Timeline.
- For more backgrounds, click **Download more** and subscribe to *GraphicStock.com*. Here you can find backgrounds, illustrations, vector graphics and design elements for every project.

Capturing screen activity

Click the **Record Screencast** button to open Movavi Screen Capture and record a new video.
[Recording screen activity](#)

Arranging files on the Timeline

Once you've added the files, they will appear on the Timeline at the bottom of the Video Editor window. The Timeline allows you to arrange the clips in the order you want. The clips' position relative to the time markers at the top of the Timeline determines when it will appear in the finished video. To reorder the clips, select the clips you want to move and then click and drag them to the new position on the Timeline.
[Learn about using the Timeline](#)



Moving a clip on the Timeline


See also:
[Working with video](#)
[Working with audio](#)

Recoding video

Follow the steps below to record video from a camera that's connected to your computer.


Step 1: Connect the camera you want to capture from to the computer. Make sure that the system recognizes the device and that it is working correctly.


Step 2: On the **Import** tab of the Video Editor, click **Record Video**. The recording module will open in a separate window.



Step 3: In the **Video capture device** box, choose the camera you want to use for capture. Then, select the **resolution** and **frame rate**. A larger resolution will be able to retain better quality, however, the video file size will be larger. A higher frame rate is necessary for recording motion, while static scenes can be captured with a lower frame rate.

Step 4: In the **Audio capture device** box, choose the microphone that you want to record the sound with.




Step 5: (Optional) By default, the recordings will be saved to your Movavi Library folder. If you want to save them somewhere else, click the folder button  under 'Save files to' and choose a different location.

Step 6: (Optional) If you want to batch rename the files, choose a renaming option from the 'File renaming' box and set up the new file name template.

Step 7: Click **Start Capture** to begin recording the video. During capture, you can take snapshots using the camera button  on the right.

Step 8: To finish the recording, click **Stop Capture**. If you need to record more videos, repeat steps 7 and 8.

Step 9: When you're done, click **Back to editing** at the bottom of the window. The captured files will be added to your project's Timeline. Also, they are saved to disk in case you want to use them later.




Recording audio

After you've added some videos and photos to the Timeline, you can record audio from a microphone or any other recording device.

Step 1: Set up recording

1. On the toolbar, click the microphone button to open audio recording options.




2. In the **Audio device** box, choose the device you want to use.

To record from a microphone: choose your preferred microphone or webcam microphone. If you don't see the device in the list, try reconnecting it to your computer.

To record audio from the computer: select **Stereo Mix** from the list. This will allow you to record any music, alerts, or other sounds playing on your computer.

3. Set the volume level you want to use in your project.

4. On the Timeline, place the progress marker to where you want the recording to begin.



Step 2: Record sound

1. When you're ready, click **Start Recording**. You will be given a 5-second countdown.

2. The video will start playing simultaneously with the recording. This way, if you're recording a voice-over, you will be able to use the video as a visual aid as you speak.


3. When you're done, click **Stop Recording**. The recorded audio clip will already be on the Timeline, as a [linked audio clip](#).

Importing AVCHD video


Follow the steps below to import previously recorded videos from an AVCHD camera.

Step 1: Connect the camera you want to capture from to the computer, and enable USB connection mode on your camera. Make sure that the system recognizes the device and that it is working correctly.

Step 2: On the **Import** tab of the Video Editor, click **Record Video**. The recording module will open in a separate window.




Step 3: In the **Video capture device** box, select your AVCHD camera.




Step 4: On the left, you will see a list of all clips on the camera storage. Review the files and deselect the ones you don't need.



Step 5: (Optional) After importing, the files will be saved to your *Movavi Library* folder. If you want to save them somewhere else, click the folder button  under '**Save files to**' and choose a different location.

Step 6: (Optional) If you want to batch rename the files, choose a renaming option from the '**File renaming**' box and set up the new file name template.


Step 7: Click **Add files to the Editor** to start copying the files. This may take a while depending on the size of the videos.



11.12.2015 18:51

00022.MTS


1824 MB



17.06.2015 16:59

17.MTS


109 MB



06.07.2015 17:03

00001111.MTS


136 MB



15.10.2015 17:52

000091111.MTS


4 MB



17.06.2015 16:59

Копия 00000 14111.MTS


109 MB



17.06.2015 16:59

Копия 00000 31111.MTS


109 MB



06.07.2015 17:03

Копия 00001 11112.MTS

136 MB



15.10.2015 17:52

Копия 00010911.MTS

4 MB

☒ Select all

Capture settings




Video capture device:
Sony Camcorder

Saving captured files

Save files to:
C:\Users\j.golenduhina\Videos\Movavi Library

File renaming:
Keep original name

Add files to the Editor



Using the Timeline

Jump to: [Timeline tracks](#) | [Zooming the Timeline](#) | [Previewing clips](#) | [Arranging clips](#) | [Position marker](#)

The Timeline, located in the bottom part of the window, is the working area that allows you to organize and edit the clips. The Timeline consists of several tracks, which are all synchronized to a single time scale at the top, which indicates the time of the project.

Timeline tracks

The Timeline is made up of several tracks, one for each media type, that allow you to arrange the clips in chronological order; mixing and joining the clips together to create your unique video.

Video track

The video track contains video clips and their attached audio, images, and transitions between clips.

- You can link audio and titles to video and image clips so that they will stay in sync as you edit the project.
- You can rotate, adjust, and use other tools on video and image clips on this track.
- You can apply [filters](#) to video and image clips on this track.

Linked audio track

The linked audio track contains audio clips that are linked to video clips. At the beginning of each linked clip, you can see a blue line that connects it to the video or image clip it is linked to. When you move, split, or delete the clip on the video track, the linked audio clip will also be edited with it. This is useful if you've synchronized the clip's audio to the video track and don't want it to change as you edit your project.


- The linked audio track is hidden at first, until you drag an audio clip between the independent audio track and the video track.
- You can edit the audio clips' volume and speed in the [Tools](#) tab.
- You can have several audio clips playing simultaneously. To do that, simply place them one under the other.

Independent audio track

The separate audio track contains audio clips that are *not* dependent on clips on the video track. This track is good for background music.

- You can edit the audio clips' volume and speed in the [Tools](#) tab.
- You can have several audio clips playing simultaneously. To do that, simply place them one under the other.

[Learn more about audio tracks](#)



Titles track

The titles track contains text clips that will appear on top of all other clips.

- You can change the titles' duration on the [Tools](#) tab, or by dragging the edge of the title's clip on the Timeline.

[Learn how to place titles](#)

Overlay track

The overlay track contains additional video and image clips to create special effects like Picture in Picture or Chroma Key.


- Clips on the overlay track are linked to clips on the video track and will stay in sync as you edit the clips.
- You can apply [filters](#) and use all of the [Tools](#) to edit the clips on this track, just like any other video or photo.
- You cannot join clips on the overlay track with [transitions](#).

[Learn about using overlays](#)

To select all clips on a single track, click the area with the track's icon to the very left of all clips.

Zooming the Timeline

To change the zoom level of the Timeline, drag the **Scale** slider at the bottom of the window. Move the slider left to zoom out, and move the slider right to zoom in on the Timeline.




Previewing clips

To preview a clip, click on it on the Timeline. The position marker will move to where you've just clicked, and the current part of the clip will be shown in the player. Click **Play** in the player to watch the video.

Rearranging clips


By default, media files will appear on the Timeline in the same order in which you've added them. To rearrange the clips, drag them with your mouse and drop them onto the desired position. To select multiple clips, use Ctrl+click and Shift+click.



Moving the position marker

The position marker defines the currently selected point on the Timeline. There are two position markers: the orange line on the Timeline, stretching down from the time scale all the way through all of the tracks, and the position marker on the progress bar of the player. Both denote the current position relative to the *whole project* and show *identical time*.

The timestamp in the player displays the currently selected time from the beginning of the project.



There are several ways to move the position marker:

- **Click** anywhere on the Timeline to move the position marker to that position.
- **Drag** the position marker (either on the Timeline, or in the player). For higher precision, try zooming in on the Timeline.
- Press the left or right **arrow key** to move to the beginning of the previous and next clip, respectively.
- To move in 0.5 second increments, open the **Playback** menu and choose **Skip Forward by 0.5 Seconds** or **Skip Backward by 0.5 Seconds**.
- To move precisely from frame to frame, use the 'Back' and 'Forward' buttons in the player. This will move the position marker exactly one frame backward or forward.

See also:
[Audio tracks](#)
[Extracting audio from video](#)

Working with video and images


After you've added some files to the project, it's time to edit them and create a beautiful video.

[Learn how to add media files](#)

Using the Timeline


When you add files to your project, they appear on the Timeline in the bottom part of the window. The Timeline allows you to view the relative length of each clip along a time scale, and make several clips play simultaneously. All videos, pictures and the transitions between them are located on the video track of the Timeline. To change the order in which they are played, simply drag-and-drop the clips to the necessary position.

[Learn more about the Timeline](#)



Cut and split video

On the Timeline, select the clip that you want to cut and move the position marker onto the moment where you want to split the clip. Then, click the scissors button on the toolbar to split the clip into two parts.




If you want to cut out a part of the video, repeat the steps to cut the unwanted fragment at the beginning and at the end, turning it into a separate clip on the Timeline. Then, select this fragment and press the **Delete** key on your keyboard. The unwanted fragment will disappear, and the remaining clips will move up the Timeline to fill in the blank space.

[Learn more about cutting videos](#)

Add filters

To apply an artistic filter to your clip, simply open the **Filters** tab and drag a filter you like onto a clip.

[Learn more about filters](#)



Picture in picture and overlays

To overlay one video or image on top of another, select the clip you want to show *on top* and drag it up, towards the top of the Timeline to create an extra overlay track. Then, double-click the upper clip to set up where the overlay will be shown on the video.

[Learn more about overlays](#)




Picture and picture, side by side overlay modes.

Using the editing Tools

The **Tools** tab also has other tools and special effects that you can use on your videos and images. To use the tools, select a clip on the Timeline and open the **Tools** tab. There, click on the tool you need and select the necessary options.

[Learn more about Tools](#)



Cutting video


Using Movavi Video Editor, you can easily split videos into parts and cut out fragments with the **Split** tool. You can find it on the toolbar of the main window, marked with a scissors icon:



Splitting video into parts


1. Select the clip that you want to split.
2. Move the [position marker](#) to the moment where you want to cut the clip.
3. Click the **Split** button on the toolbar.

Note that if the clip has [linked audio](#), the audio clip will also be split.



Cutting out fragments

1. Select the clip you want to cut and move the position marker to the beginning of the unwanted fragment.
2. Click the **Split** button. The clip will be cut into two parts, with the unwanted fragment at the beginning of the second clip.
3. Select the second clip and move the position marker to the end of the unwanted fragment.
4. Click the Split button again. The fragment is now a separate clip.
5. Select the clip with the unwanted fragment and click the **Remove** button (trash can icon), or use the **Delete** key on the keyboard. The clip will be removed, and the remaining clips on the Timeline will move to close the gap.



For more precise navigation:

- Use the arrow keys to jump to the beginning of the previous or next clip on the Timeline.
- Open the **Playback** menu and use the **Skip Forward by 0.5 Seconds** or **Skip Backward by 0.5 Seconds** commands to jump half a second forward or back.
- Use the keyboard shortcuts to move the position marker half a second back and half a second forward, respectively: Shift+Ctrl+Left and Shift+Ctrl+Right.
- Use the Previous Frame and Next Frame buttons for precise frame-by-frame navigation. You can also use the Ctrl+Left and Ctrl+Right keyboard shortcuts.



Applying filters

Using filters you can alter the mood of the video, make an old movie, overlay cool flying objects, and more.


Step 1: Open the Filters tab

Click the **Filters** button to open the filters collection. Click on a filter's thumbnail to see its preview in the player. If you're looking for a specific filter, you can enter its name into the search box.



Step 2: Apply the filter

When you've found a filter you like, drag its thumbnail onto the clip you want to apply the filter to.





Once you've applied a filter, a star icon will appear on the clip, denoting applied filters and tools.



Clip with an applied filter

Removing filters

To remove a filter, click on the star  icon on the clip to see the list of applied filters and tools. In the list, select the filter that you don't want and click **Remove**.



Adding overlays

Overlays are video or image clips that are shown over the main video. You can use these to create a split screen or picture in picture effect, add a logo or watermark, or insert a short clip without cutting the main video.


Before you start:

You'll need to add both the main video (the video that will be the bottom layer) and the overlay video or image to your project. You can use images in PNG format to add transparent logos.

Step 1: Place the overlay clip

1. Select the clip that you want to make an overlay and drag it *up*, towards the top of the Timeline.
2. Drop the clip onto the overlay track, where you want it to be shown relative to the main video track.

Note that a blue line now connects the overlay clip to the main clip. This means that the overlay clip is linked to the main clip: if you move, cut, or delete the main clip, the overlay clip will also be edited.



Step 2: Edit the overlay

1. Double-click the overlay clip to set it up. An options panel will appear in the player.
2. Open the drop-down box on the overlay panel and choose how you want it to appear on the video: **Picture in picture**, **Side by side**, or **Cover**.



Picture in picture


This is the default overlay mode. Using picture in picture mode, you can show the overlay video over any part of the screen.


1. Choose **Picture in picture** mode from the drop-down box.
2. In the player, move the overlay to where you want it to appear in the frame.
3. To resize the overlay, drag at its corners.
4. Deselecting the **Constrain proportions** option will allow you to resize the overlay to any proportions, but a drastic change in proportions may make the overlay look distorted.



Picture in picture overlay

Side by side

1. Choose **Side by side** mode from the drop-down box.
2. Use the buttons on the panel to choose how you want to align the two videos: 



Side by side overlay

Cover

Cover mode can be used for a short insert into the main video without having to cut it. While the main video (and audio!) is playing, the overlay clip will appear on screen for the duration of the overlay clip.



Cover overlay (the main clip is hidden)

Step 3: Apply the changes

After you've set up the overlay, click the **Apply** button on the overlay options panel.

Step 4: Overlay clip tools

You can also edit each overlay clip's speed and opacity. To do that, use the **Volume**, **Speed**, and **Opacity** sliders in the General section of the **Tools** tab. Keep in mind that you can also use other clip editing tools on overlay photos and videos!


[Learn more about tools](#)

Editing tools


The **Tools** tab allows you to edit the selected clip and add special effects. To use the tools:

Step 1: On the Timeline, select the clip that you want to edit. This can be a video or an image clip on any track. Also, you can edit the volume for audio clips.

Step 2: Click the **Tools** button on the left side of the window to open the Tools tab. Here, you will find the selected clip's basic properties, such as volume and speed.




Step 3: Choose the tool that you want to use and click on it to see more options.

Step 4: Set up the tool however you want to use it. Don't forget to click **Apply** to keep the changes! After you've used a tool on the clip, it will be marked with a star icon , denoting applied tools or filters.



Removing the changes

On the clip, click the star icon to show the list of applied tools. Then, select the tool you want to discard and click **Remove**. Also, you can deselect the tool on the **Tools** tab.



General clip properties

At the top of the Tools tab, you can edit the basic clip properties including volume, speed, opacity and duration.

Volume – can be used to adjust the loudness of video and audio clips. 100% is the original clip's volume.

Speed – can be used to speed up or slow down video and audio clips.

Opacity – can be used to make overlays transparent. [Learn about overlays](#)


Duration – can be used to set how long the selected image or titles clip will appear on screen.

Fade in, Fade out – can be used to smoothly fade a video or sound. [Learn more](#)

Color adjustments

You can use automatic enhancements for your videos and photos, improving contrast, saturation, and white balance. Select a clip and click the **Color Adjustments** button on the toolbar to open the enhancement options.


[Learn more about enhancements](#)



Crop video

When you open the **Crop** tool or click the **Crop** button on the toolbar, a frame will appear inside the player. Use this frame to crop the video and click **Apply** to accept the changes.


[Learn more](#)



Rotate video and images

Using the **Rotate and Flip** tool, you can rotate videos by 90°, flip them vertically or horizontally, or apply a cool mirror effect.

[Learn more](#)



Zoom

With the **Zoom** tool, you can create a panning or zooming effect. Choose a zooming mode and then set the zoom target using the frame in the player and click **Apply**.

[Learn more](#)



Zooming and panning

Chroma key

Using the **Chroma key** tool, you can remove a color from an entire video and replace the background with any other video or photo.

[Learn more](#)



Replacing a green background with the Chroma Key effect.

Highlight and conceal

Use this tool to blur or darken a part of the video. This way you can hide certain objects, like license plates or other private information, or highlight things you want to show!

[Learn more](#)



Left to right: no effect, soft focus, conceal.

Stabilizing videos

Use the stabilization tool to remove camera shake from your footage.

[Learn more](#)




Before and after stabilizing

Video volume


This section explains how to manage the volume of video clips. To change the volume of audio clips, refer to the [Volume levels](#) section.

Step 1: On the Timeline, select the video that you want to edit.

Step 2: Click the **Tools** button to open the tools for the selected clip.



Step 3: Drag the **Volume** slider to set the volume for the selected clips.100% is the original volume. To mute the clip, drag the slider down to 0%.




Speed

With the Speed tool, you can speed up or slow down a video or audio clip. This can be useful if you're working on a music video and you want the video to match the tempo of the music.


Step 1: On the Timeline, select the clip you want to edit.

- Note that slowing down videos works best on videos with a frame rate of 60 FPS (frames per second) and above.
- You can also change the speed of any audio clip.
- If you modify the speed of a video with built-in audio, the audio speed will also be changed.

Step 2: Click the **Tools** button to open the editing tools for the selected clip.



Step 3: Drag the **Speed** slider to set the necessary video speed, where 100% is the video's original speed.



You can see the current length of each slide right under its preview on the storyboard. If you've changed video speed, the video clips will be marked with a speed icon:




Changing image duration


By default, all images will be shown for 4 seconds each. To change the duration:

Step 1: On the Timeline, select the image clip that you want to edit.


Step 2: Click the **Tools** button to open the tools for the selected clip.



Step 3: In the **Duration** box, enter the new length of the image. Use the following format: *hours:minutes:seconds.milliseconds*. Changes will be applied instantly.



You can also change image duration by selecting an image clip on the Timeline and dragging its borders left or right. The longer the clip appears on the Timeline, the longer it will play in your movie or slideshow.




Fading video and audio

In the editing tools, you can add smooth fades to the beginning or the end of a clip. For videos and images, you can use fading simultaneously with animated transitions. For audio clips, you can create a smooth crossfade effect between songs.

Step 1: On the Timeline, select the clip that you want to fade.


Step 2: Open the **Tools** tab.



Step 3: Set the fade length using the sliders in the **General** section of the Tools tab

- **Fade in** – how long in seconds it will take to fade in to full opacity at the beginning of the clip.
- **Fade out** – how long in seconds it will take to fade out from full opacity at the end of the clip.

To create an audio **crossfade**, add a fade out to the first clip, and a fade in effect to the second clip.



See also:
[Adding transitions](#)

Color adjustments


If the original videos look bleak and not vibrant enough, you can use the automatic adjustments to make the colors look more vivid. If that isn't enough, you can always use manual adjustments to correct the colors.

Step 1: Select clip

On the Timeline, select the clip that you want to adjust.


Step 2: Open color adjustments

On the toolbar, click the color adjustments button to open the adjustments in the **Tools** tab.



Step 3: Use auto adjustments

Under **Color Adjustments**, select the adjustment options that make the selected clip look nicer. The changes will be applied instantly. The **Magic Enhance** option will automatically determine the best brightness and contrast balance.



Step 4: (Optional) Use manual adjustments

Click the **Manual Adjustments** button to show more color control options. Here, drag the sliders to fix the brightness, saturation, hue, and other properties. To go back to the simple options, click the **Auto Adjustments** button underneath the sliders.



Once you have used the adjustments, the clip will be marked with a star icon, denoting applied tools or filters: 




Cropping video

Cropping a video can help you remove black bars, cut away the edges of the video, or permanently zoom in onto an object inside the frame.

Step 1: On the Timeline, select the clip you want to crop.


Step 2: Click the **Crop** button on the toolbar. The Crop tool will open in the **Tools** tab, and a cropping frame will appear inside the player.



Step 3: In the player, set the frame so that the parts you don't want are outside it.

- Drag by the corners of the frame to change its size.
- Drag by the center of the frame to change its position.
- By default, the frame will have the same proportions as your project. If you want to change the proportions, deselect the **Constrain proportions** option. However, note that black bars may appear around the video after if the video's proportions are different from the project's.

Step 4: Click **Apply** in the Tools tab. A star icon will appear on the clip once you've applied crop.



Removing crop

To remove Crop or any other Tools effect, do any of the following:


- Click the star icon on the clip to show the list of applied effects and filters. In the list, select Crop and click the Remove button to discard the effect.
- In the **Tools** tab, you'll see a checkmark next to Crop. Click the circle with the checkmark to remove the effect.

Cropping all clips

Step 1: Open the **Edit** menu and choose **Project Settings** to edit your project. The Project Settings window will open.

Step 2: In the **Resize Method** box, choose **Crop**.

Step 3: Click **OK**. All the project's clips will be automatically cropped to the project's frame size.



Rotate and flip clips

Nobody likes vertical videos! But don't worry, in just a few clicks, you can turn any vertically-shot photo or video around without having to crane your neck.

Step 1: Select clip


On the Timeline, select the clip you want to rotate.

Step 2: Open rotation tools

Click the **Rotate** button on the toolbar to open the rotation options in the **Tools** tab.

Step 3: Flip and rotate

Click the arrow buttons to rotate the clip clockwise or counterclockwise or flip it along the horizontal or vertical axis. The changes will be applied instantly. Here, you can also create a cool mirroring effect.




Zooming clips

Using the **Zoom** tool, you can draw attention to an object inside the frame by magnifying it, or pan a virtual camera across the frame.

Step 1: On the Timeline, select the clip that you want to zoom.

Step 2: Click the **Tools** tab, scroll the tool list down and click the **Zoom** tool. The Zoom settings will open, and a frame will appear inside the player. You can use this frame to select which part of the video you want to zoom.




Step 3: On the Tools tab, select the Zoom mode:

- **Zoom in-out** — the clip will start at 100%, zooming in on the object, and then zooming back out to 100%.
- **Zoom in** — the clip will start at 100% and then zoom in on the object until the end of the clip.
- **Zoom out** — the clip will start already zoomed in, and then slowly zoom out to 100% towards the end of the clip.
- **Pan right** — this mode uses two frames. The clip will start at the position of the left frame, and then pan to the position of the right frame.
- **Pan down** — this mode uses two frames. The clip will start at the position of the upper frame, and then move down, to the position of the bottom frame.
- **Pan and zoom left** — this mode uses two frames. The clip will start at 100% (larger frame), and then zoom in to the smaller frame.

Step 4: Set up the zoom level and position using the frames in the player.

- In modes that use one frame, move the frame over the object that you want to zoom.
- In modes with two frames, place the first frame to where you want the clip to start, and the second frame to where you want the clip to end. During playback, the virtual camera will smoothly move from one frame to the other.




The size of the frame determines the zoom level, that is, the part of the frame that will be visible at the maximum zoom. The smaller the frame, the higher the zoom level. If both frames are of the same size, the zoom level will not change. If the frames have different sizes, the zoom level will smoothly change when moving from one frame to another.

Hint:

For best results, use high-definition videos and photos for zooming, since setting a very high zoom level may lower the quality in zoomed parts.

Step 5: In the Zoom section of the Tools tab, click the **Apply** button.



Chroma key

Replacing a video's background


The Chroma key effect allows you to remove any color from the image or video, leaving the background transparent.

Step 1: Add the foreground and background clips

Add the video or image clips that you want to use as the foreground and the background. For the foreground (the clip that you want to remove the background from), use a clip with a bright, solid background that contrasts with the foreground objects.


Step 2: Create an overlay

1. Select the foreground video and move it up, onto the **Overlay track**.
2. Double-click the foreground video on the Overlay track. The overlay options will appear above the player.
3. To make the foreground video completely cover the background video, select the **Cover** overlay mode from the list above the player.
4. Click **Apply**.




Step 3: Apply Chroma key

1. Select the foreground video on the Overlay track.
 2. Open the **Tools** tab, scroll to the bottom and click the **Chroma Key** tool to see its options.
 3. Once you open the **Chroma Key** tool, move your mouse cursor over the player and click on the color that you want to remove. The color you've picked will be made transparent, and the underlying video will now be visible.
- Tip: if nothing happens when you click on the player, click the color swatch in the Chroma Key options and then try again.*



4. Use the **Tolerance** slider to set how many similar shades of the selected color should also be removed. Higher values will remove similar colors to the one you've selected.
5. Use the **Noise level** slider to determine how sharp the object's edges should be.
6. Finally, click **Apply** to accept the changes.



Cropping the video

If the videos you're using for the foreground and background have different aspect ratios, you may end up with black bars along the edges after applying Chroma key. To fix this, crop the videos to the project's aspect ratio.


[How to remove black bars](#)
[Cropping videos](#)

Highlight and conceal


Using the **Highlight and Conceal** tool, you can control the focus in the frame, and blur or darken select parts of the video.

Step 1: On the Timeline, select the clip that you want to edit.

Step 2: Click the **Tools** button, scroll down, and click the **Highlight and Conceal** tool. The tool's options will open, and a frame will appear in the player.



Step 3: In the **Highlight and Conceal** tool options, select a mode that suits your needs:




- **Conceal** — blurs or darkens the area inside the frame.
- **Highlight** — blurs or darkens the area *outside* the frame, drawing attention to the object within the frame.



- **Outline** — like 'Highlight' mode, the area outside the frame is blurred or darkened, and the frame itself is outlined.
- **Soft focus** — the edges of the frame are much softer than other modes, simulating a camera's focus.



Step 4: Choose how you want to highlight or conceal the object: using a rectangle or an ellipse, blurring or darkening. Set the **Transparency** level to change the effect intensity.




Step 5: In the player, move the frame over the object that you want to highlight or conceal.

Stabilizing video


If you're filming with a handheld camera, it's likely that there might be some unwanted camera shake visible on the video, especially if you walk or move while filming.

Step 1: On the Timeline, select the clip you need to stabilize.

Step 2: Open the **Tools** tab. Scroll down and click the **Stabilize** tool.



Step 3: Under **Stabilize**, click **Apply** to start stabilizing the selected clip. This may take a couple minutes for large clips.



Stabilized copies

A stabilized copy of the file will be created under *My Videos\Movavi Screen Capture Studio\Stabilized*. This copy will be used in the project instead of the original video. If you delete the stabilized copy, it will be replaced with the original video, and you will need to stabilize the clip again.

Filming tips:


- When shooting videos, try to rest the camera on something.
- If possible, use a tripod. Some tripods are really small and can fit into your bag.
- If you can't put down the camera, hold it with both hands and close to your body. This will minimize the shaking.
- Try to move around less. If you have to move the camera, do it slowly.
- Check your camera's settings to see if it has built-in stabilization.

Working with audio

Add audio

You can add audio the same way as you would add video and images: on the **Import** tab, click the **Add Media Files** button under **My files** and choose the audio files you want to use. If you don't have suitable audio files you can use free music themes from the **Sample audio** collection.

[Learn more about adding audio](#)




Audio tracks

The Timeline consists of video and audio tracks for each type of media. There are two types of audio track: linked audio and independent audio.

Linked audio clips, located on the upper audio track, allow you to 'attach' sound to a point on a video clip, so that when you move or split the video, the audio will also be moved and split with the video. This is especially useful if you're adding a voice-over and want it to stay synchronized to the video throughout the editing process. To link an audio clip to video, drag an audio clip up towards the video clip you want to attach it to, and align the beginning of the audio with the place on the video clip when you want the audio to start. A blue line will connect the video clip to its linked audio.


Independent audio clips stay on the lowermost audio track, and play independent from any other tracks. For example, you can place a background music clip on this track, and it will play throughout the project. By default, all new audio files will be added as independent audio.

[Learn more about audio tracks](#)



Extract audio from video


When you add a video to your project, both the video and its soundtrack will be located on the video track. The soundtrack is shown as a line underneath the video track. To separate the audio from its video clip, drag-and-drop the audio *down* to the independent audio track. You've just extracted the soundtrack from a video file! If you don't need the original video, feel free to delete it from the timeline by pressing the **Delete** key on your keyboard. Don't worry, the audio will remain where you've put it.



Set volume levels

You can set volume levels independently for each video and audio clip.


1. Select the clip that you want to edit.
2. Open the **Tools** tab.
3. In the **General** tools, drag the **Volume** slider to set the necessary volume where 100% is the volume of the original clip.



Split audio

You can cut and split audio clips the same way as you would work with video. To split an audio clip into two parts:

- 1. Select the audio clip you want to split
- 2. Move the position marker to where you want to cut the video.
- 3. Click the **Split** button (scissors icon) on the toolbar and the audio will be split into two parts.



Loop audio

If the background music ends before your movie does, you can loop the music clip to continue playing until the end:


- 1. Copy the music clip.
- 2. Paste it onto the audio track nearby as many times as necessary, until the music is as long as the video. Make sure that the clips are aligned side-by-side and do not overlap.
- 3. Now, the last looped clip is probably longer than the video. To trim it from the end, drag the rightmost edge of the audio clip to the left, so that the audio clip ends when you want it to.

Adding audio

You can add audio files in much the same way as you add video files.

Add files from your hard drive

1. On the **Import** tab, click **Add Media Files** to browse for audio files on your computer.
2. A Windows Explorer dialog box will open. Choose the files that you want to use.
3. Click **Open**. The files will be added onto the audio track of the Timeline.



Use sample audio clips

If you don't have any suitable audio files, you can use free sample audio clips^[1] from the Movavi Video Editor audio collection.


1. On the **Import** tab, click **Sample audio** to open the free stock audio collection.
2. Click on a clip to play it. When you've picked a clip, drag it onto the audio track of the Timeline.



Record audio


1. Connect a microphone to your computer.
2. On the Timeline, place the position marker to where you want the recording to start.
3. Click the microphone button on the toolbar to open recording options.
4. Set up your recording device and volume.
5. Click **Start Recording** and record the audio. When you're finished, click **Stop Recording**. You'll find your new recording on the Timeline.

[Learn more about audio recording](#)



Set start time for audio clips

After you've added the audio files, they will appear on the audio track of the Timeline as a blue line with a music note icon:



By default, the audio clips will be added to the very beginning of the audio track on the Timeline. To change when the audio clip starts playing, drag it along the Timeline.

[Learn about audio tracks](#)

[1] Stock Audio Tracks:

Stock audio tracks are copyright of their respective owners and are **free** for both personal and commercial use with credit attribution under the [Creative Commons license](#).

Adventure
"Coulda Shoulda Buddha" by UncleBibby

Mystic
"Lunar Dunes" by Spinning Clocks

Available on the Free Music Archive (freemusicarchive.org) [Under CC BY license](#)

Romantic

"The Wrong Way" by Jahzzar

Available on the Free Music Archive (freemusicarchive.org) [Under CC BY-SA license](#)

Available on the Free Music Archive (freemusicarchive.org) [Under CC BY license](#)


Travel

"Nobody Here But Us Charles Dickens" by UncleBibby

Available on the Free Music Archive (freemusicarchive.org) [Under CC BY license](#)


Audio tracks

When you add new audio files, they will be added to the audio track of the Timeline.



Audio clip on the Timeline

There are two kinds of audio track: *independent audio* track and *linked audio* track.



Independent audio

The bottom audio track is the independent audio track. Audio clips on this audio track will play independent of any other clips, which is perfect for background music. By default, all newly added audio clips appear on the independent audio track.


Linked audio

The linked audio track appears when you attach an audio clip to a video clip. Linking an audio clip to a video means that the audio clip will always be synchronized with this video clip, as if it was part of the video file. This is especially useful if you want to add a voice-over and make sure it stays synchronized with the video as you continue working on the project.

- Linked audio can be 'attached' to any point of a video clip, whenever you want the audio to start.
- If the linked audio is longer than the video it is attached to, it will keep playing when the video clip ends.
- If you move the video clip, its linked audio clips will also be moved, without losing sync with the video.
- If you delete the video clip, the linked audio clips will also be deleted.
- If you split the video clip, the linked audio clip will also be split into two parts, each linked to the same points of the video as they were before.

To link an audio clip:

1. Drag the audio clip *up*, towards the video track. The linked audio track will appear – this is where you will need to place the audio clip.
2. A blue line will appear, connecting the beginning of the audio clip to a point on the video clip. This line marks when the audio clip will start playing relative to the video clip. Drop the audio clip onto the linked audio track, so that the blue line is at the point when you want the audio to start.




Drag the clip up to attach it to a video.

Embedded audio on the video track


Video clips are usually made up of video and audio streams. When you add a video to the Timeline, it will be added to the video track as a video clip with an audio clip underneath it. Whenever you move or split a video, its audio will also be moved and split with the video.

If you want to edit the video's soundtrack separately, you can detach it from the video clip: drag the audio clip from underneath the video *down* onto the independent audio track.



Playing audio synchronously

If you want two audio clips to play at the same time, simply drag one clip underneath the other. This way, you can have as many sub-tracks as you want. With music, you can use this to create a crossfade effect when you join songs: align the beginning of the second song with the end of the first song to make them joined almost seamlessly.



The end of the first audio clip will be played with the beginning of the second clip.

Problem: My audio clip appears on the video track


Solution: Some audio files contain album art, which may sometimes be recognized as the video stream. Therefore, these files may be placed on the audio track. In that case, drag the audio clip *down* onto the audio track, and delete the album art from the video track if you do not need it.

Volume levels


Changing volume levels works the same way for video and audio clips:

Step 1: On the Timeline, select the clip that you want to edit. This can be a video or an audio clip on any track.

Step 2: Click the **Tools** button to open the tools for the selected clip.



Step 3: Drag the **Volume** slider to set the necessary level, where 100% is the original volume. To mute the clip, drag the slider down to 0%.



Playback volume

Only for previewing

If you need to temporarily change the volume of playback in the editor, without changing the project's volume, click the speaker icon in the preview area and set the necessary volume level. Please note that this will only affect the volume while previewing the project in Movavi Video Editor, and will not affect the output file.



Cutting audio


Splitting audio

1. Select the clip that you want to split.
 2. Move the position marker to the point where you want to split the clip.
 3. Click the **Split** button on the toolbar (scissors icon).
- The audio clip will now be split into two parts.



Trimming audio

To trim an audio clip from the beginning or from the end, hold your mouse pointer over the left or right edge of the clip and drag it towards the center. The length of the audio clip on the Timeline reflects the length of the sound.



Cutting out parts

Let's say you want to cut out a fragment from the middle of an audio clip. This is done the same way as splitting video and audio, except that you will need to split the clip twice.


1. Split the audio clip at the beginning of the unwanted fragment. To do that:
 - 1.1 Select the clip you want to cut.
 - 1.2 Find the beginning of the unwanted fragment and move the position marker there.
 - 1.3 Click the **Split** button on the toolbar (scissors icon).

This will split the clip into two parts, with the unwanted fragment located in the beginning of the second clip.

2. Split the audio clip at the end of the unwanted fragment. To do that:
 - 2.1 Select the second clip.
 - 2.2 Find the end of the unwanted fragment and move the position marker there.
 - 2.3 Click the **Split** button again.

The fragment is now located in a separate clip.

3. Now, select the clip with the unwanted fragment and press the **Delete** key on your keyboard. The clip will be removed, and the remaining clips will be moved up to close the gap.



For more precise navigation:


- Use the arrow keys to jump to the beginning of the previous or next clip on the Timeline.
- Open the **Playback** menu and use the **Skip Forward by 0.5 Seconds** or **Skip Backward by 0.5 Seconds** commands to jump half a second forward or back.
- Use the keyboard shortcuts to move the position marker half a second back and half a second forward, respectively: Shift+Ctrl+Left and Shift+Ctrl+Right.
- Use the Previous Frame and Next Frame buttons for precise frame-by-frame navigation. You can also use the Ctrl+Left and Ctrl+Right keyboard shortcuts.



Looping audio

If the music file you've selected doesn't go all the way until the end of your movie, you can loop the audio and have the file play over again until the end of the video.

- 1. Copy the audio clip. To do that, right-click the audio clip on the Timeline, and choose **Copy** from the pop-up menu, or use the Ctrl+C keys.
- 2. Paste the audio clip onto the Timeline right next to the first clip. The clip will be inserted right after the position marker. Repeat until the audio is as long as the video.
- 3. Now, the audio track may be longer than the video track. To trim the audio, hold your mouse pointer over the right edge of the clip, and drag the edge to the left, until the end of the audio clip is right under the end of the video clip.




Extracting audio from videos

If you want to use a soundtrack from a movie, you can extract it from a video file and use it in your project.

Step 1: Open video file


On the **Import** tab, click **Add Media Files** and choose the video that contains the music you want. The file will be added to the video track of the Timeline.



Step 2: Trim video


If you don't need the whole video's soundtrack, you can trim away the parts of the video you won't need. It's easier to do this with the video file, as the video can help you visually find the beginning and end of the fragment you need.

1. Select the video you want to trim.
2. Move the position marker to the beginning of the fragment you want to keep and click the Split button on the toolbar (scissors). You've just cut off the beginning of the video.
3. Now, select the second clip and move the position marker to the end of the fragment you need. Click the Split button again, and the fragment will now be in a separate clip.
4. If you don't need the other fragments, select them on the Timeline and click the trash can button on the toolbar to delete them.



Step 3: Extract the video

The audio that belongs to a video is shown right underneath it on the video track. To separate it from the video, drag the audio stripe down onto the audio track. If you don't need the video clip anymore, go ahead and delete it.



You can now work on the extracted audio clip.

Step 4: Save the audio (optional)

If you want to save the audio clip for later use, you can export it as an audio file:

1. Click the **Export** button. The export window will open.
2. In the **Export** window, switch to the **Save Only Audio** tab.
3. Select an audio format that you want to save the audio file in.
4. The Save to field shows where on the disk the file will be saved. To change that folder, click **Browse** and select a new folder.
5. Finally, click **Start** to save the audio file.


Please respect copyright laws and stay within the boundaries of fair use of copyrighted materials.

Adding titles

Adding text titles to your movie allows you to express your thoughts and supplement the audio with subtitles.

Step 1: Go to the Titles tab


On the left-hand side of the window, click the **Titles** button to view the titles collection. Click on a title style's thumbnail to preview its looks in the player and choose the titles you want to use.



Step 2: Add a titles clip

To add titles to your project, pick a title style you like and drag its thumbnail onto the title track of the Timeline, right above the video track. A title track will appear above the video track: drop the titles here, onto the time where you want them to appear. The titles will appear as a purple ribbon on the Timeline.

The beginning of each title clip is linked to a corresponding video clip on the video track. This way, whenever you move or edit the video clip, its titles will always stay in sync.




If you already have a titles clip on the Timeline, you can add another clip onto the same timeframe to make them play simultaneously: simply place one title clip under another.

Step 3: Edit titles

When you've added a title clip, it will start out with the default text and looks. Double-click the title's ribbon on the Timeline to show editing options in the player.


Title clip properties


Click the cogwheel icon  at the top of the editing panel to see title clip properties. Here, you can change the **duration** of the titles and **animation speed** (how fast they will appear or disappear).

Editing text

1. In the preview, click on the text box you want to edit to select it.


2. Enter the new text.

3. Click the **Font properties**  button and select the font style, size, and alignment options for the selected text.


4. Click the **Color properties**  button and choose a color for the text, and the outline's width and color.

5. Drag the text box to where you want to see it on the video.

Editing decoration elements

Some titles come with frames, ribbons, and other decorations. To change their color, select the decoration element you want to edit and click the **Color properties**  button. Then, click the **Decorations** color palette and choose the new color.

Finally, click **Apply** to exit editing mode.




Adding transitions


Transitions are short animations that use geometric shapes and transparency to connect two clips in a creative way.

Add a transition


1. Click the **Transitions** button in the upper left-hand corner of the window to open the list of all transitions.



2. In the list of transitions, pick a style you like and drag-and-drop its icon between two clips on the Timeline.



A transition icon will appear between the two clips.




Change transition length

By default, each transition will be set at 2 seconds long. To change the transition length:

1. Double-click a transition on the Timeline to open transition properties.

2. In the **Transition Properties** window, enter the new transition length in the **Duration** field. The format is *hours:minutes:seconds:milliseconds*. If you want all transitions that are currently in the project to have the same length, select the Set this duration for all transitions option.

3. Click **OK** to apply the changes.




Add transitions to all clips

You can automatically add transitions between all clips in your movie in just a few steps:


1. Click the slideshow button on the toolbar. The Create Slideshow dialog box will open.
2. In the **Create Slideshow** dialog box, select a transition style that you want to use for all clips. If you want to use different transitions, use the **Random Transitions** option in the list of transitions.
3. In the **Transition duration** box, enter the length that you want to set for all transitions. A transition cannot be longer than the shortest clip in your project.

4. Click **OK** to accept the changes.
[Creating Slideshows](#)



Remove a transition

To remove a transition from your movie or slideshow, right-click the transition on the Timeline and choose **Remove Transition** from the pop-up menu. If you want to delete all the transitions in your project, choose **Remove All Transitions**.




Creating slideshows

With Movavi Video Editor, you can easily create a slideshow in just a few simple steps:

Step 1: Add videos and photos

On the **Import** tab, click **Add Folder** in the **My files** section to add the contents of an entire folder (for example, all your vacation photos!) or click **Add Media Files** to add individual files.

[Adding media files](#)




Step 2: Add transitions and set slide duration

Now that you've added the media files, they will appear on the Timeline. Now it's time to set the length of each slide and join them with interesting transitions.

1. Click the slideshow button on the toolbar.
2. In the **Create Slideshow** dialog box, select a transition style that you want to use for the slideshow. If you want to use different transitions, choose the **Random Transitions** option.
3. In the **Image slide duration** field, enter how long you want each slide to be shown on screen. The format is *hours:minutes:seconds:milliseconds* for both transitions and slides.
4. In the **Transition duration** field, enter the length for all transitions. Transition length cannot exceed slide length.
5. Click **OK** to accept the changes and add the transitions.

If you want to change individual transitions, go to the **Transitions** tab and drag the transition you want in between two clips on the Timeline.

[Learn more about transitions](#)



Step 3: Add background music

To add music, go back to the **Import** tab and click the **Add Media Files** button to choose a background audio file. If you don't have suitable audio files on your computer, you can use one of our sample music tracks: click **Sample audio** on the **Import** tab to open the stock audio collection and drag an audio sample onto the Timeline.

[Learn more about adding audio](#)


[Learn more about working with audio](#)

Step 4: Add titles

To add text to your slideshow:

1. Go to the **Titles** tab.
2. Drag a text style you like onto the *top* of the Timeline and drop it onto the titles track.
3. Double-click the titles ribbon to edit the clip.
4. In the player, enter your text and set up the font and color options.
5. Click **Apply** on the options panel to accept the changes.


[Learn more about adding titles](#)




Step 5: Save your slideshow

Finally, it's time to save your slideshow.

- 1. Click the **Export** button in the bottom right-hand corner of the window.




- 2. In the **Save as Video** tab of the **Export** window, choose the format that you want to save the video in. This will affect video quality and file size.
- 3. The **Save to** box shows where the video file will be saved to. If you want to choose a different location, click **Browse**. After that, name your slideshow in the **File Name** box.
- 4. Click **Start** to begin processing your slideshow! This may take up to a few minutes, depending on the size of your slideshow.



How to get rid of black bars


Sometimes, when you use videos of different aspect ratios, or if the project is set up incorrectly, some videos may have black bars around them. This can be fixed by adjusting the project settings, so that they fill up the whole frame.




Some clips have black bars around them

If some videos or photos have black bars around them, it is most likely that they have a different aspect ratio from that defined in the [project settings](#). For example, even videos and photos shot with the same camera may differ in width and height, so that when you place them side by side, one of them may end up with black bars. To fix this, you can crop away the edges of those clips, so that they fill the entire frame:

1. Beneath the Timeline, find the **Project settings** information and click the pencil icon next to it to open the project settings window.




2. Open the **Resize Method** box and select **Crop** from the list.
3. Click **OK**.



All clips have black bars around them


If all of the clips have black bars around them, then it's a good idea to change the aspect ratio of the project to match that of the clips you are using.

1. First, you'll need to find out the size of the videos you are using, so that you can match it in project settings. To do that, right-click a clip on the Timeline and choose **File Information** from the pop-up menu. Here, note the **width x height** size of the frame (e.g. 1920x1080) and the **aspect ratio** (e.g. 16:9).




Now we'll need to set the project settings to the same frame size.

2. Beneath the Timeline, find the **Project settings** information and click the pencil icon next to it to open the project settings window.



3. Under **Frame Size**, choose the frame size with the same aspect ratio as your videos. If you can't find it in the list, you can manually input the frame size into the boxes below.

4. Click **OK** to accept the changes. The clips should now nicely fit inside the frame without any black bars.




Exporting videos

When you're done with your project, you'll need to export it as a media file to be able to play it back in media players, mobile devices, and so on. This section will guide you through the process of exporting your project to a popular video format. If you want to find out more about other ways of saving videos, see the following guides:

- [Saving only audio](#)
- [Saving videos for devices](#)
- [Saving videos for uploading online](#)

Step 1: Open the Export window

To start saving the video, click the **Export** button in the bottom right-hand corner of the Editor. The export settings window will open.




Step 2: Choose a format


Open the list at the top of the window and choose a format for saving the video in. Some formats allow you to choose which video codec you want to use, and some allow you to save 60 FPS video*.

*The video file will have a frame rate of 60 FPS only if the original video files used in the projects had a frame rate of 60 FPS and above.


If you don't know which format to choose, try using **MP4 with the H.264 codec**. The MP4 format is supported by most platforms and operating systems.



Step 3: Check your project settings

When saving standard video, the video will be exported with the same settings that were set for the project. This way, the output video will appear exactly as you have seen it in the preview area. If you want to change the resolution, aspect ratio, or other settings, click the pencil icon  to view and edit the project settings.

The **Estimated File Size** field shows how much disc space your file will require after saving. If the file size is too large, you can set a lower resolution in the [Project Settings](#). At lower resolutions, the file will be significantly smaller, however, the video will lose some quality due to the limitations of digital data compression. When changing resolutions, we recommend that you keep the same aspect ratio to avoid black bars around the video or other unwanted distortions. [Learn more about project settings](#)



Step 4: Select quality (optional)

If your project is heavy on small details and filters, you can select **High** or **Highest** quality to export the finished video with a higher bitrate. This will increase the output file size but will preserve better quality. For most other projects, **Good** quality will provide a nice result at a small file size.

Step 5: Choose a destination folder

Name your file and choose a destination folder.

In the '**Save to**' field, enter the folder where you would like to store the file. By default, this will be the directory for saving output videos specified in the [preferences](#). To set a different folder, click the **Browse** button and choose the folder in the Windows Explorer window, or enter the path manually into the box. Name your video in the **File Name** field: the project's name will be filled in for you by default.

Save as Video

Save Only Audio

For Apple Devices

For Android Devices

For Other Devices

For Uploading Online

AVI with H.264 codec

Project Settings: 1280x720 16:9 29.97 FPS, 44100 Hz Stereo

Export Settings: 1280x720 16:9 29.97 FPS, 44100 Hz Stereo

Estimated File Size: 88 MB

Quality:

Good

High

Highest

Save to: E:\Temp\Videos

Browse

File Name: SampleProject

Start

Cancel

Step 6: Start exporting
Click the **Start** button to begin processing the video file. This may take up to a few minutes.

Save as Video

Save Only Audio

For Apple Devices

For Android Devices

For Other Devices

For Uploading Online

AVI with H.264 codec

Project Settings: 1280x720 16:9 29.97 FPS, 44100 Hz Stereo

Export Settings: 1280x720 16:9 29.97 FPS, 44100 Hz Stereo

Estimated File Size: 88 MB

Quality:

Good

High

Highest

Save to: E:\Temp\Videos

Browse

File Name: SampleProject


Start

Cancel


Export only audio

This section will guide you through exporting just the audio track of your project.

Step 1: Click the **Export** button in the bottom right-hand corner of the Editor to open the export settings window.



Step 2: At the top of the Export window you will find a number of tabs. Click on the **Save Only Audio** tab



Step 3: Open the list at the top of the tab and select the format you'd like to save the audio in.

While MP3 is the most commonplace format, supported by almost all media players and devices, FLAC format allows you to preserve high audio quality, albeit taking up considerably more disc space. When choosing an output format, it is important to note the quality of the original files: due to data compression limitations, digital audio cannot be restructured from very low quality files by saving them as FLAC audio, and vice versa – high quality files may lose some of that quality when saved to MP3 format which is limited to 320 Kbps.

When saving audio from your project, the audio file will retain the same sample rate and channel settings as you have set for your project. The audio bitrate will be determined from the quality of the original files and from the maximum bitrate for the selected format (for example, MP3 is limited to 320 Kbps, while FLAC bitrate is not limited).

Step 4: Name your file and choose a destination folder. In the '**Save to**' field, enter the folder where you would like to store the file. By default, this will be the directory for saving output videos specified in the [preferences](#). To set a different folder, click the **Browse** button and choose the folder in the Windows Explorer window, or enter the path manually into the box. Name your video in the **File Name** field: the project's name will be filled in for you by default.


Step 5: Click the **Start** button to begin processing the video file. This may take up to a few minutes.



Export for devices


This guide will help you export your video project for playing on mobile phones, tablets, TVs, and other devices.

Step 1: In the bottom right hand corner of the Editor, click the **Export** button to open the export settings window.



Step 2: At the top of the Export window, you will find a number of tabs for saving different kinds of media. Choose the necessary tab depending on your type of device:

- **For Apple Devices:** to save the video for devices made by Apple, including iPhones, iPads, iPods and Apple TV.
- **For Android Devices:** to save the video for smartphones, tablets, and other devices running the Android operating system.
- **For Other Devices:** to save the video for devices running neither iOS nor Android. These include Blackberry and Nokia smartphones, classic mobile phones with 3GP and 3G2 video, Xbox, PlayStation, Zune, and others.



Step 3: Once you've opened the necessary tab, open the list at the top and select your device or manufacturer from the list.

Note the **Export Settings** information, where you can view the properties for the output file. Due to the limitations of some devices, the video resolution, audio quality, and other properties may be changed to adhere to the requirements of the selected device. **Estimated File Size** will give you a rough estimate of how much disk space the file will occupy, which may be important if your device is running out of memory.

Step 4: Set export quality (optional).
If your project is heavy on small details and filters, you can select **High** or **Highest** quality to export the finished video with a higher bitrate. This will increase the output file size but will preserve better quality. For most other projects, **Good** quality will provide a nice result at a small file size.

Step 5: Name your file and choose a destination folder.
In the '**Save to**' field, enter the folder where you would like to store the file. By default, this will be the directory for saving output videos specified in the [preferences](#). To set a different folder, click the **Browse** button and choose the folder in the Windows Explorer window, or enter the path manually into the box. Name your video in the **File Name** field: the project's name will be filled in for you by default.


Step 6: Click the **Start** button to begin processing the video file. This may take up to a few minutes.




Export online

When exporting your video project, you can prepare it for uploading to YouTube and other video hosting sites.

Step 1: When your project is complete, click the **Export** button in the bottom right hand corner of the Editor to open the exporting window.



Step 2: The upper part of the Export window contains a row of tabs. Click **For Uploading Online** to open the list of relevant settings.



Step 3: Open the list at the top of the tab and choose a suitable format for saving your video.

For YouTube and other video sharing websites:

If you want to upload the video to a video hosting website, such as YouTube, you can simply choose one of the available presets, such as **YouTube - 720p**. For some, you can choose to save the video in a variety of resolutions: for example, you can choose HD or standard-definition video when saving for Vimeo. However, if the original videos are of HD quality, we recommend that you choose a higher resolution, as the video sharing service will automatically create a lower-resolution copy of your video for low-bandwidth viewers.

Please note that some video sharing websites, such as Vimeo, limit HD video uploads for different types of accounts. We advise you to check the website's upload restrictions, as well as any copyright policies, and to make sure that you have the right to publish the videos in question under copyright laws and your country's law.
[YouTube Help – Increasing your upload limit](#)
[Vimeo FAQ](#)

For your own website or web storage:

At the bottom of the list, you can find a number of web-ready formats. Choose the one that best fits your upload requirements. You can also embed YouTube videos into your blog or website: simply save your video using one of the YouTube options, upload the video to your YouTube account, go to your video's page and then click **Share**, and go to the **Embed** tab. YouTube will give you an HTML5 embed link for your video that you can use in your website or blog.

Note the **Export Settings** section, where you can see the properties that your output video will be saved with. These properties are defined by the selected format, resolution, or the requirements of the chosen video sharing website.

Step 4: Select video quality (optional).

If your project is heavy on small details and filters, you can select **High** or **Highest** quality to export the finished video with a higher bitrate. This will increase the output file size but will preserve better quality. For most other projects, **Good** quality will provide a nice result at a small file size.

Step 5: Name your file and choose a destination folder.

In the '**Save to**' field, enter the folder where you would like to store the file. By default, this will be the directory for saving output videos specified in the [preferences](#). To set a different folder, click the **Browse** button and choose the folder in the Windows Explorer window, or enter the path manually into the box. Name your video in the **File Name** field: the project's name will be filled in for you by default.

Step 6: Click the **Start** button to begin processing the video file. This may take up to a few minutes.




Saving and opening projects

A project stores all the work on your movie or slideshow. You can save the project for finishing your work later, or restore your work if you need to edit something after you've finished.

Saving the project

1. Open the **File** menu and choose **Save Project**.
2. You will be asked to enter a name for the project. Your project files should be stored in the "*Videos\Movavi Screen Capture Studio\Projects*" folder of your user.
3. Click **Save** to confirm saving.



Later, you can open this project to continue working on your project.

Opening a project

1. Open the **File** menu and choose **Open Project**.
2. Locate the project file.
3. Click **Open** in the dialog box.


You can now resume your work on the project.

See also:
[Finding missing files](#)
[Project settings](#)
[Exporting videos](#)

Finding missing files

When you open a previously created project, you may see a message saying that a file is missing from the project. This may happen if one of the files used in the project has been moved somewhere else or deleted from disk.

- If the file was moved elsewhere, click the **Browse** button and locate the file in the Windows Explorer window. After that, you can continue working on the project as usual: the file will be restored in its place on the timeline, as well as any other changes you have made.
- If the file was deleted or you no longer wish to use it in the project, click **Skip** to open the project without the missing file.
- To cancel loading the project, click **Cancel**.



Why is this happening?

In order to save disk space, the program does not copy the files you add to the project, but rather remembers their location on disk. Therefore, if you move or delete the original files, it will no longer be able to use them as reference.


Project settings

You can set up your project's video and audio settings both when creating the project and at any other time.


Opening Project Settings


When creating a project:

When you create a new project or launch Movavi Video Editor, you will see a small window where you can choose an aspect ratio for your project. Click **Advanced Settings** to show more video and audio settings.



During editing:

- On the bottom panel of Movavi Video Editor, find the pencil icon next to the information about your project. 
- Open the **Edit** menu and choose **Project Settings**.
The **Project Settings** window will open.



Video Settings

The video settings apply to all videos and photos used in the project. When you import the media files, they will be scaled to fit inside the selected frame size according to your settings.


Frame size

The *frame size* or *resolution* determines the videos width and height in pixels. Open the **Frame Size** list to select from the most common resolutions. For your convenience, each resolution is marked with its respective aspect ratio. Ideally, the frame size should match the resolution of the videos and photos you plan to use in your project, and should not exceed the resolution of the largest video. Smaller resolutions allow you to make the output video smaller and thus save your disc space, however, this will sacrifice some video quality due to downscaling.

Frame Size	Aspect Ratio
320x240	4:3
640x480	4:3
1280x720	16:9
1280x960	4:3
1920x1080	16:9
1920x1440	4:3


Aspect ratio

The *aspect ratio* is the ratio of the video or photo's width to its height. The most commonly used aspect ratios are 4:3, used generally for analog TV and in many old movies, and 16:9, the standard resolution for widescreen digital video.





A relative comparison of aspect ratios

When you add videos and photos to the project, they will be scaled to fit the specified frame size. If you add media files with an aspect ratio different from that of the project, you may see black bars appear on the sides of the video. Furthermore, if you add low-quality videos to a project set up to a high resolution (frame size), the small video may be stretched to fit the frame and thus may appear pixellized. For best results, we recommend setting the frame size and aspect ratio to match all or most of the videos and photos you are planning to use.



Examples of black bars appearing when importing videos with a different aspect ratio.

If you cannot find the necessary frame size in the list, you can manually enter the width and height into the respective boxes of the **Project Settings** window. Note the button with the link icon to the right of the boxes. It allows you to maintain existing proportions when entering new values:  – the proportions are constrained, allowing you to set a larger or smaller frame size without changing the aspect ratio;  – you can freely enter the width and height with any proportions. Simply click this button to toggle the two states.

Resize method

Choosing a resize method can help you manage how all of your videos and photos are resized to fit inside the frame size you've set. This is especially important when the aspect ratio of some videos and photos does not match the aspect ratio of the project and you need to get rid of the black bars. There are three resizing options available:

Letterbox – the video will be resized to fit inside the frame entirely. This method allows you to keep the whole video inside the frame without distortions, but may place black bars around the video.



Stretch – the video is fit entirely inside the frame and then stretched on one axis in such a way as to fill the entire frame without leaving black bars. This allows you to cover the entire frame, however, the objects in the video may appear horizontally or vertically distorted.



Crop – the video will be resized to be slightly larger than the frame, cropping the parts that do not fit inside it. This allows to cover the entire area of the frame without distorting any of the objects inside the video or without leaving black bars, however, this may not suit some clips where important objects are near the edge of the frame.



Audio Settings

Sample rate


The *sample rate* affects the quality of digital sound, and defines the maximum frequencies that an audio stream can contain. The default sample rate is set to 44100 Hz, which exceeds the maximum frequencies of human hearing and is used to record Audio CDs and most music tracks.

Channels


Stereo sound contains two channels and has the capacity to convey the relative location of sound sources, which makes it best for recording music; **mono** sound has only one channel and produces sound without differentiating left and right channels. Stereo is the generally preferred number of channels, however, some mobile devices record sound only in mono mode.

File properties

To open a file's properties, right-click or Ctrl+click it on the storyboard and choose **File Information** from the context menu. Knowing certain information about a clip will allow you to better understand which settings are best for your videos.



A small **File Information** window will appear. Here, you can find out the video or image's **resolution**, **aspect ratio**, and other properties.



See also:
[Creating a project](#)
[Saving and opening projects](#)

Program preferences

To open the preferences, open the **Settings** menu and select **Preferences**.

Interface Language – to change the interface language, simply select the necessary language from the list and click **OK** to apply the changes.

Directory for project files – this folder will be offered by default when saving and opening projects. This folder will also store any autosave files for new projects. You can use the autosave file to restore your work in case of an error or force close.

Directory for saving output videos – this folder will be offered by default when exporting media files.

Directory for audio recordings – the audio clips that you record in the Editor will be stored as audio files in this folder. *Tip: if you delete these audio files, the audio recordings in the project will also be unavailable.*

Directory for stabilized files – when you stabilize a video, a stabilized copy of the original will be created in this folder and used instead of the original. *Tip: don't delete these files while you are working on the project, or you'll have to stabilize the files again.*

Automatically check for updates – select this option and you'll be notified whenever a new version is available. Updates within your version are absolutely free (e.g. 1.0 to 1.1), while new releases are offered with a hefty discount to registered users.

Send anonymous usage stats to Movavi – checking this box will allow the program to send usage statistics to our development team, enabling us to fix any bugs you may encounter much faster, as well as add new features that you might be missing. The data contains no personal information, will not be disclosed to third parties and will be used for software improvement purposes only.

[Learn more about how we use the statistics](#)

[Read our Privacy Policy](#)

Show project settings window when creating new project – with this option enabled, you will be prompted to select settings for the new project on startup and when creating new projects. You can choose the project's aspect ratio and other settings, as well as open an existing project.

Enable Intel® hardware acceleration – if this option is available, your computer is equipped with an Intel HD Graphics™ chip. Enabling this option will allow using this graphic chip during exporting to accelerate video processing by up to 400%.

[Learn more](#)

When you're done, click **OK** to close the window and apply the preferences.

Help and support

If you have any questions or concerns regarding Movavi software, you are welcome to contact our support team.

Write to us at support@movavi.com

Or click the button on the right to ask a support specialist via live chat.

Please describe your problem in as much detail as possible; any screenshots or log files will allow us to help you faster. Our support team specialists may ask you for additional information that is required to solve your problem: these may include your license key, log files, and files you were working with, but never personal information. We value your privacy!

Have you checked the [FAQ section](#)?
Your question may have already been answered!

Frequently asked questions:

[How to remove trial restrictions?](#)

[Why do my videos have "trial version" on them](#)

[What are the system requirements for running Movavi Screen Capture Studio?](#)

[What formats can I save my videos in?](#)

[How to update the graphics card drivers?](#)

System requirements

	Minimum system requirements	Recommended configuration
Operating system	Windows XP*/Vista/7/8/10 with latest service packs and patches	
Processor	Intel, AMD or compatible processor, 1.5 GHz	Intel, AMD or compatible processor, 2.8 GHz and above
Graphics card	NVIDIA® GeForce™ series 6 or higher, AMD Radeon™ R600 or higher graphics card with up-to-date drivers**	
Resolution	1024x768, 32-bit color	1280x1024 or higher
RAM	Windows XP – 512 MB Windows Vista, 7, 8, 10 – 1 GB	Windows XP – 1 GB Windows Vista, 7,8, 10 – 2 GB
Available disk space	810 MB for installation 2 GB for ongoing operations***	10 GB
Administrator permissions are required for installation		
Additional features		Sound card for audio recording and playback
		Intel® hardware acceleration requires a compatible Intel processor supporting Intel HD Graphics™ 2nd generation or higher Learn more
		For intended performance, make sure that your graphics card drivers are up-to-date. Updating graphics card drivers

* *Windows XP does not support recording system sound simultaneously with audio devices.*

** *Your graphics card must support OpenGL for the program to run correctly.*

*** *Free disk space is required to save the temporary recording file and the output video. The required amount of disk space will depend on the resolution, format, and length of your videos.*

Movavi Screen Capture Studio may also run on slower machines, however, we cannot guarantee stable performance if the minimum requirements are not met.

Input formats

These are the file formats that you can use in the Video Editor.

Video Formats	Supported Codecs
3GPP (.3gp), 3GPP2 (.3g2)	H.263, H.264, MPEG-4
Advanced Streaming Format (.asf)	MPEG-4, VC-1, WMV V7
Audio Video Interleave (.avi)	H.264, MPEG-4, H.263, MJPEG, DivX, Xvid, DV, Cinepack, Fraps, TechSmith, Uncompressed
DivX Video (.divx)	DivX
Flash (.flv)	H.264, FLV1, H.263, Flash Screen Video
Flash (.swf)	FLV1
HD Video (.m2ts, .mkv, .mov, .mp4, .mpg, .wmv)	MPEG-2, MPEG-4, H.264, WMV V8
HD Video (.m2t, .mts, .ts, .wmv)	MPEG-2, MPEG-4, H.264, AVCHD, WMV 9, WMV 9 Advanced profile
Matroska (.mkv)	H.264, MPEG-4, MJPEG, Theora, DV, Uncompressed
MPEG Transport Stream (.m2ts)	H.264
MPEG Transport Stream (.ts, .mts, .m2t)	MPEG-2, H.264
MPEG (.mpg)	MPEG-1, MPEG-2
MPEG (.mpeg, .mpe, .m1v, .mod, .tod)	MPEG-1, MPEG-2, H.264
MPEG-4 (.mp4)	MPEG-4, H.264, H.263, MJPEG, ProRes
MPEG-4 (.m4v)	MPEG-4, H.264, H.263, MJPEG, ProRes
MXF – Material eXchange Format (.mxf)	MPEG-2, DV
OGV – Ogg Video (.ogv)	Theora, MPEG-4
QuickTime (.mov)	H.264, MPEG-4, AIC, MJPEG, ProRes, Sorenson 1/3, PNG
RM – RealMedia (.rm, .rmvb)	Real Video 2/3/4, Cooker
WebM (.webm)	VP8, VP7, VP9
WMV – Windows Media Video (.wmv)	WMV V8, WMV V7, WMV 9, WMV 9 Screen, WMV 9 Advanced profile, MPEG-4, WMV 9.1 Image V2
WTV – Windows Recorded TV Show (.wtv)	H.264, MPEG-2
Audio Formats	Supported Codecs
AAC – Advanced Audio Coding (.aac)	AAC
AIFF – Audio Interchange File Format (.aif,.aiff)	Uncompressed
APE – Monkey's Audio (.ape)	Monkey's Audio
Au (.au, .snd)	PCM
FLAC – Free Lossless Audio Codec (.flac)	FLAC
MP3 – MPEG-1/2 Audio Layer III (.mp3)	MP3
MPEG-4 (.m4a)	AAC
OGG – Ogg Audio (.ogg)	Vorbis
WAV – Waveform Audio File Format (.wav)	PCM, AAC, MP3
WMA – Windows Media Audio (.wma)	WMA 9, WMA Pro, WMA Voice
AMR – Adaptive Multi-Rate audio codec (.amr, .3ga)	AMR
Image Formats	
BMP, DPX, GIF, JPEG (.jpeg, .jpg, .jp2, .jls), MJPEG, JPEGLS, Netpbm formats (.pgm, .pbm, .ppm, .pam), PCX, PNG, PTX, SGI, TARGA (.tga), XBM, XWD	

Output formats	
Video Formats	Supported Codecs
3GPP (.3gp), 3GPP2 (.3g2)	H.263, H.264, MPEG-4
Audio Video Interleave (.avi)	H.264, MPEG-4, MJPEG
Flash (.flv)	FLV1, H.264
Flash (.swf)	FLV1
Matroska (.mkv)	H.264, MPEG-4, MJPEG, Theora
MPEG Transport Stream (.m2ts)	MPEG-2, H.264
MPEG (.mpg, .vob)	MPEG-1, MPEG-2
MPEG-4 (.mp4)	MPEG-4, H.264
OGV – Ogg Video (.ogv)	Theora
QuickTime (.mov)	H.264, MPEG-4
WebM (.webm)	VP8
WMV – Windows Media Video (.wmv)	WMV V8
Audio Formats	Supported Codecs
AAC – Advanced Audio Coding (.aac)	AAC
FLAC – Free Lossless Audio Codec (.flac)	FLAC
MP3 – MPEG-1/2 Audio Layer III (.mp3)	MP3
OGG – Ogg Audio (.ogg)	Vorbis
WAV – Waveform Audio File Format (.wav)	PCM
WMA – Windows Media Audio (.wma)	WMA 9

Supported Devices

Movavi Screen Capture Studio supports a wide variety of devices from old and faithful classics to the newest flagships. You can find the full list of supported formats and devices [here](#).

Updating graphics card drivers

If you encounter an error message asking you to update your graphics drivers, you will need to download a new driver from your graphics card manufacturer's website and install it on your system. Some graphics card drivers also have a useful utility that notifies you when a driver update is available and updates the driver automatically. Keeping your graphics card drivers up-to-date will ensure stable performance of applications and games on your computer.

Step 1: Find your graphics card manufacturer

1. Right-click your desktop and choose **Screen Resolution**
2. In the Screen Resolution settings window, click **Advanced settings**.
3. This will open your graphics card properties. At the top of the window, your graphics card model will be listed under the **Adapter Type** section. Note the full name of the graphics card somewhere for later.

Step 2: Download the new version

Now that you've learned your graphics card manufacturer and model, go to the manufacturer's website and find driver downloads. There, look for the model or series that you've found earlier and download the driver installation file. Some manufacturers may also offer a utility that will automatically find the necessary driver.

[NVIDIA Download Center](#)

[AMD Download Center](#)

Warning:

Only download drivers from the official manufacturer's website. Third-party websites offering driver downloads may contain malware.


Step 3: Install driver

Once the file is completely downloaded, run the installation file and follow the onscreen instructions to install the driver on your system. Your display may blink several times in the process. After the installation has finished, it is advised that you restart the computer.

Updating NVIDIA® Driver

Modern NVIDIA graphics cards come with a special application called **NVIDIA GeForce™ Experience** that monitors driver updates and allows you to optimize your computer's graphics performance.

1. Open the **NVIDIA GeForce Experience** application. It should already be installed on your system. If you cannot find the application, please try the method above.
2. In the **Drivers** section, click the **Check for updates** button to find the latest drivers.
3. When the application has found a newer driver, click the **Download driver** button. From here, the software will automatically download and install the necessary driver for your system.



Updating AMD® or ATI® Driver

1. If you have an AMD or ATI graphics card, go to the Driver Download Center on AMD's official website.
[AMD Driver Download Center](#)
2. Download the auto detect utility and run it when the download has finished.
[Auto Detect Utility](#)
3. The utility will then automatically find your graphics card and help you download and install the right driver for your system.

If the utility fails to find a driver for you, you can manually select your graphics card model and operating system on the Driver Downloads page and download the driver.

4. After the driver has downloaded, run the installation file and follow the on-screen instructions to install it.
5. After the driver has been installed, it is recommended that you restart your computer.

If none of the above steps have helped, feel free to contact our support team via e-mail or live chat.

support@movavi.com

If possible, please include the name of your graphics card model (see Step 1), as well as screenshots of any error messages you have encountered. This will help our support team specialists solve your problem quicker.

Hardware acceleration

If your computer is equipped with an Intel® HD Graphics chip, the output videos can be saved much faster by sharing the workload between the processor and the graphics clip, boosting processing speed up to 400%.

Supported codecs

You can use Intel acceleration when saving videos using the H.264 and MPEG-2 codecs.

Enabling Intel acceleration

1. Open the **Settings** menu and click **Preferences**.
2. In the Preferences window, select the **Enable Intel hardware acceleration** option.
3. Click OK to accept the changes.

Troubleshooting

If the acceleration option is unavailable it may mean one of the following:

- Your computer is not equipped with an Intel HD Graphics chip
- The Intel HD Graphics chip is not recognized because the driver is out of date. To fix this, you can download and install the driver from the manufacturer's website. You can find the newest version at the official Intel website here: [Intel Download Center](#)